

**Exim4 - Dovecot SASL** ..... 3

..... 3

..... 3

..... 3

Dovecot ..... 3

Exim4 ..... 4

..... 4

..... 4


..... 5



— 2015/07/29 10:30

# Exim4 - Dovecot SASL

- Debian 8
- Exim4



- Exim4                      exim4-daemon-light가                      exim4-daemon-heavy
- dovecot

```
[user@host]# apt-get install exim4-daemon-heavy dovecot-core
```


## Dovecot

dovecot-core

### /etc/dovecot/conf.d/10-master.conf

```
service auth {
...
#SASL
  unix_listener auth-client {
    mode = 0660
    user = Debian-exim
  }
...
}
```

### /etc/dovecot/conf.d/10-auth.conf



```
auth_mechanisms = plain login
```

## Exim4

Dovecot SASL unix socket

가

### **/etc/exim4/exim4.conf.template**

```
dovecot_login:
  driver = dovecot
  public_name = LOGIN
  server_socket = /var/run/dovecot/auth-client
# setting server_set_id might break several headers in mails sent by
authenticated smtp. So be careful.
  server_set_id = $auth1

dovecot_plain:
  driver = dovecot
  public_name = PLAIN
  server_socket = /var/run/dovecot/auth-client
  server_set_id = $auth1
```

```
[user@host]# update-exim4.conf -d /etc/exim4 -o /etc/exim4/exim4.conf
[user@host]# systemctl restart dovecot.service
[user@host]# systemctl restart exim4.service
```

```
root@mail:~# telnet localhost 25
Trying ::1...
Connected to localhost.
Escape character is '^]'.
220 mail.koov.net ESMTPEXIM 4.84 Mon, 27 Jul 2015 15:03:31 +0900
EHLO koov.net
250-mail.koov.net Hello koov.net [::1]
250-SIZE 52428800
250-8BITMIME
250-PIPELINING
250-AUTH LOGIN PLAIN
250 HELP
```

```
AUTH LOGIN
334 VXN1cm5hbWU6
a29vdg==
334 UGFzc3dvcmQ6
dGVzdDEyMzQ=
235 Authentication succeeded
```

- <http://wiki2.dovecot.org/HowTo/EximAndDovecotSASL>
- [Base64](#)

From:  
<https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:  
[https://atl.kr/dokuwiki/doku.php/exim4\\_-\\_dovecot\\_sasl](https://atl.kr/dokuwiki/doku.php/exim4_-_dovecot_sasl)

Last update: **2015/07/29 01:30**

