


Exim4 - Dovecot SASL 3
..... 3
..... 3
..... 3
Dovecot 3
Exim4 4
..... 4
..... 4

Exim4 - Dovecot SASL

- Debian 8
- Exim4



- Exim4 exim4-daemon-light가 exim4-daemon-heavy
- dovecot

Dovecot

dovecot-core

/etc/dovecot/conf.d/10-master.conf

```

service auth {
...
#SASL
  unix_listener auth-client {
    mode = 0660
    user = Debian-exim
  }
...
}

```

/etc/dovecot/conf.d/10-auth.conf

```

auth_mechanisms = plain login

```

Exim4

Dovecot SASL unix socket

가

/etc/exim4/exim4.conf.template

```
dovecot_login:
  driver = dovecot
  public_name = LOGIN
  server_socket = /var/run/dovecot/auth-client
# setting server_set_id might break several headers in mails sent by
authenticated smtp. So be careful.
  server_set_id = $auth1

dovecot_plain:
  driver = dovecot
  public_name = PLAIN
  server_socket = /var/run/dovecot/auth-client
  server_set_id = $auth1
```

```
[user@host]# update-exim4.conf -d /etc/exim4 -o /etc/exim4/exim4.conf
[user@host]# systemctl restart dovecot.service
[user@host]# systemctl restart exim4.service
```

```
root@mail:~# telnet localhost 25
Trying ::1...
Connected to localhost.
Escape character is '^]'.
220 mail.koov.net ESMTP Exim 4.84 Mon, 27 Jul 2015 15:03:31 +0900
EHLO koov.net
250-mail.koov.net Hello koov.net [::1]
250-SIZE 52428800
250-8BITMIME
250-PIPELINING
250-AUTH LOGIN PLAIN
250 HELP
AUTH LOGIN
334 VXNlcm5hbWU6
```

```
a29vdg==  
334 UGFzc3dvcmQ6  
dGVzdDEyMzQ=  
235 Authentication succeeded
```

From:

<https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:

https://atl.kr/dokuwiki/doku.php/exim4_-_dovecot_sasl?rev=1437977076

Last update: **2015/07/27 06:04**

