

RHEV Self-Hosted Backup/Restore 3

RHEV Self-Hosted Backup/Restore

— 2017/02/15 19:07

Self hosted engine

- Self-Hosted 가 (Self-Hosted host 1)
- RHEV-M Backup Data 가
- 가

```

0. Global Maintenance mode ( , )

1. rhvm backup
   engine-backup --scope=all --mode=backup --file=BACKUP_FILE --
log=LOG_FILE
2. hosted-engine shutdown
   hosted-engine --vm-shutdown
3. host

2. selfhost ( RHEVM VM )
3. rhvm VM OS update
4. install rhvm
5. engine-setup

6. service ovirt-engine stop
7. engine-cleanup

8. restore db
su - postgres -c psql
alter role engine encrypted password 'PASSWORD';
engine-backup --mode=restore --scope=all --file=rhev3.6.backup --
log=restore.log --change-db-credentials --db-host=localhost --db-name=engine
--db-user=engine --db-password --restore-permissions

9. engine-setup

10. delete hosted_engine VM from db
delete from snapshots where snapshot_id=(select snapshot_id from
snapshots where vm_id=(select vm_guid from vm_static where vm_name like
'HostedEngine'))
delete from vm_static where vm_guid=(select vm_guid from vm_static where
vm_name like 'HostedEngine')

11. manager UI hosted_engine host -> ->

```

12. selfhost

From:

<https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:

https://atl.kr/dokuwiki/doku.php/rhev_self-hosted_backup_restore

Last update: **2017/02/16 06:40**

