RHEV 3.6 hosted-engine gateway

RHEV 3.6 hosted-engine gateway

: RHEV 3.6

gateway

.

Put the cluster in global maintenance.

```
# hosted-engine --set-maintenance --mode=global
```

Stop the HA services on all hosts:

```
# systemctl stop ovirt-ha-agent.service
# systemctl stop ovirt-ha-broker.service
```

hosted-engine

```
# dir=`mktemp -d` && cd $dir
# sdUUID_line=$(grep sdUUID /etc/ovirt-hosted-engine/hosted-engine.conf)
# sdUUID=${sdUUID_line:7:36}
# conf_volume_UUID_line=$(grep conf_volume_UUID /etc/ovirt-hosted-
engine/hosted-engine.conf)
# conf_volume_UUID=${conf_volume_UUID_line:17:36}
# conf_image_UUID_line=$(grep conf_image_UUID /etc/ovirt-hosted-
engine/hosted-engine.conf)
# conf_image_UUID=${conf_image_UUID_line:16:36}
# dd if=/rhev/data-
center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID
2>/dev/null| tar -xvf -

#                hosted-engine                                          .
#          fhanswers.conf                                  answers
     .

# cp /etc/ovirt-hosted-engine/answers.conf.rpmsave fhanswers.conf # or edit
answers.conf as you need.
```

.

```
# tar -cO * | dd of=/rhev/data-
center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID
```

Start the HA services on all hosts:

```
# systemctl start ovirt-ha-broker.service
# systemctl start ovirt-ha-agent.service
```

Disable global Maintenance:

```
# hosted-engine --set-maintenance --mode=none
```

- https://access.redhat.com/solutions/2348341

From:
https://atl.kr/dokuwiki/ - **AllThatLinux!**

Permanent link:
https://atl.kr/dokuwiki/doku.php/rhev_3.6_hosted-engine_gateway_%EB%B3%80%EA%B2%BD

Last update: **2019/09/05 06:12**