

<b>CentOS 7</b>	<b>ovs</b>	.....	3	
<b>RPM</b>		.....	3	
1.		.....	3	
2.	"ovs"	. "root" .	.....	3
3.	"ovs"	.	.....	3
4.	RPM	.	.....	3
5.	가	.	.....	3
6.		.....	4	
		.....	4	

Last update:  
2021/07/02  
12:57

centos\_7\_  
\_ovs\_

[https://atl.kr/dokuwiki/doku.php/centos\\_7\\_%EC%97%90\\_ovs\\_%EC%84%A4%EC%B9%98?rev=1625230620](https://atl.kr/dokuwiki/doku.php/centos_7_%EC%97%90_ovs_%EC%84%A4%EC%B9%98?rev=1625230620)

---

# CentOS 7 ovs

CentOS7

EPEL

RPM

RPM

## RPM

1.

```
$ yum -y install wget openssl-devel gcc make python-devel openssl-devel
kernel-devel graphviz kernel-debug-devel autoconf automake rpm-build redhat-
rpm-config libtool python-twisted-core python-zope-interface PyQt4 desktop-
file-utils libcap-ng-devel groff checkpolicy selinux-policy-devel gcc-c++
python3-devel python3-sphinx unbound unbound-devel
```

2. "ovs" "root"

```
$ adduser ovs
$ su - ovs
```

3. "ovs"

Open vSwitch : <https://www.openvswitch.org/download/> 2.15.1 LTS  
2.13.4 LTS

```
$ mkdir -p ~/rpmbuild/SOURCES
$ wget https://www.openvswitch.org/releases/openvswitch-2.13.4.tar.gz
$ cp openvswitch-2.13.4.tar.gz ~/rpmbuild/SOURCES/
$ tar -xvf openvswitch-2.13.4.tar.gz
```

4. RPM

```
$ rpmbuild -bb --nocheck openvswitch-2.13.4/rhel/openvswitch-fedora.spec
```

5. 가

```
$ yum localinstall
```

```
/home/ovs/rpmbuild/RPMS/x86_64/openvswitch-2.13.4-1.el7.x86_64.rpm -y
```

6.

```
$ systemctl enable openvswitch.service  
$ systemctl restart openvswitch.service
```

```
$ ovs-vsctl -V  
ovs-vsctl (Open vSwitch) 2.13.4  
DB Schema 8.2.0
```

- <https://gist.github.com/umardx/a31bf6a13600a55c0d07d4ca33133834>
- <https://www.linuxtechi.com/install-use-openvswitch-kvm-centos-7-rhel-7/>
- <https://bryan.wiki/276>

From:  
<https://at1.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:  
[https://at1.kr/dokuwiki/doku.php/centos\\_7\\_%EC%97%90\\_ovs\\_%EC%84%A4%EC%B9%98?rev=1625230620](https://at1.kr/dokuwiki/doku.php/centos_7_%EC%97%90_ovs_%EC%84%A4%EC%B9%98?rev=1625230620)

Last update: **2021/07/02 12:57**

