

JBoss EAP 7 max-post-size	3
 JBoss EAP 6.x/7.x max-post-size	3
 JBoss EAP 6.x/7.x post size limit	4
EAP 6	4
EAP 7	4
	5

JBoss EAP 7 max-post-size

JBoss EAP 6.x/7.x max-post-size

- JBoss EAP 6.x : $2097152 = 2\text{MiB}$

가

```
[standalone@localhost:9999 /]
/subsystem=web/connector=http:read-resource(include-runtime=true)
{
    "outcome" => "success",
    "result" => {
        .....
        "max-connections" => undefined,
        "max-post-size" => 2097152,                                     <<<<<<<<<
        "max-save-post-size" => 4096,
        "maxTime" => 0,
        .....
    }
}
```

- JBoss EAP 7.x : $10485760 = 10\text{MiB}$

가

```
[standalone@localhost:9990 /] /subsystem=undertow/server=default-
server/http-listener=default:read-resource(include-runtime=true)
{
    "outcome" => "success",
    "result" => {
        "allow-encoded-slash" => false,
        .....
        "max-parameters" => 1000,
        "max-post-size" => 10485760L,                                     <<<<<<<<
        "max-processing-time" => 0L,
        .....
        "url-charset" => "UTF-8",
        "worker" => "default",
        "write-timeout" => undefined
    }
}
```

JBoss EAP 6.x/7.x post size limit

EAP 6

EAP 6 max-post-size 0

```
[standalone@localhost:9999 /]
/subsystem=web/connector=http:write-attribute(name=max-post-size, value=0)
```

xml

```
<subsystem xmlns="urn:jboss:domain:web:2.2" default-virtual-server="default-host" native="false">
    <connector name="http" protocol="HTTP/1.1" scheme="http" socket-binding="http" max-post-size="0"/>
    <virtual-server name="default-host" enable-welcome-root="true">
        <alias name="localhost"/>
        <alias name="example.com"/>
    </virtual-server>
</subsystem>
```

EAP 7

EAP 7.2+ max-post-size 0 . EAP 7.1
0 . Long.MAX_VALUE(9223372036854775807)

```
[standalone@localhost:9999 /] /subsystem=undertow/server=default-server/http-listener=default/:write-attribute(name=max-post-size,value=0)
```

xml

```
<subsystem xmlns="urn:jboss:domain:undertow:3.1">
    <buffer-cache name="default"/>
    <server name="default-server">
        <http-listener name="default" max-post-size="0" socket-binding="http" redirect-socket="https"/>
        <host name="default-host" alias="localhost">
            <location name="/" handler="welcome-content"/>
            <filter-ref name="server-header"/>
            <filter-ref name="x-powered-by-header"/>
        </host>
    </server>
</subsystem>
```

```
</server>
```

- <https://access.redhat.com/solutions/714173>

From:
<https://atl.kr/dokuwiki/> - AllThatLinux!



Permanent link:
https://atl.kr/dokuwiki/doku.php/jboss_eap_7_max-post-size_%EB%B3%80%EA%B2%BD

Last update: **2023/01/09 08:24**