JBoss EAP 7 max-post-size

JBoss EAP 6.x/7.x max-post-size

- JBoss EAP 6.x : 2097152= 2MiB

```
[standalone@localhost:9999 /]
/subsystem=web/connector=http:read-resource(include-runtime=true)
{
    "outcome" => "success",
    "result" => {
            ........................
        "max-connections" => undefined,
        "max-post-size" => 2097152,                          <<<<<<<<<<<
        "max-save-post-size" => 4096,
        "maxTime" => 0,
            ........................
    }
}
```

- JBoss EAP 7.x : 10485760 = 10MiB

```
[standalone@localhost:9990 /] /subsystem=undertow/server=default-
server/http-listener=default:read-resource(include-runtime=true)
{
    "outcome" => "success",
    "result" => {
        "allow-encoded-slash" => false,
        ........................
        "max-parameters" => 1000,
        "max-post-size" => 10485760L,                        <<<<<<<<<<<
        "max-processing-time" => 0L,
        ........................
        "url-charset" => "UTF-8",
        "worker" => "default",
        "write-timeout" => undefined
    }
}
```

JBoss EAP 6.x/7.x   post size limit

EAP 6

EAP 6   max-post-size   0   .

```
[standalone@localhost:9999 /]
/subsystem=web/connector=http:write-attribute(name=max-post-size, value=0)
```

                  xml   .

```
<subsystem xmlns="urn:jboss:domain:web:2.2" default-virtual-server="default-
host" native="false">
    <connector name="http" protocol="HTTP/1.1" scheme="http" socket-
binding="http" max-post-size="0"/>
    <virtual-server name="default-host" enable-welcome-root="true">
        <alias name="localhost"/>
        <alias name="example.com"/>
    </virtual-server>
</subsystem>
```

EAP 7

EAP 7.2+   max-post-size   0   . EAP 7.1
         0   . Long.MAX_VALUE(9223372036854775807)
       .

```
[standalone@localhost:9999 /] /subsystem=undertow/server=default-
server/http-listener=default/:write-attribute(name=max-post-size,value=0)
```

                  xml   .

```
<subsystem xmlns="urn:jboss:domain:undertow:3.1">
    <buffer-cache name="default"/>
    <server name="default-server">
        <http-listener name="default" max-post-size="0" socket-
binding="http" redirect-socket="https"/>
        <host name="default-host" alias="localhost">
            <location name="/" handler="welcome-content"/>
            <filter-ref name="server-header"/>
            <filter-ref name="x-powered-by-header"/>
        </host>
```

```
      </server>
```

  * https://access.redhat.com/solutions/714173

From:
https://atl.kr/dokuwiki/ - **AllThatLinux!**

Permanent link:
https://atl.kr/dokuwiki/doku.php/jboss_eap_7_max-post-size_%EB%B3%80%EA%B2%BD

Last update: **2023/01/09 08:24**