

<b>JBoss EAP 7 parameter size</b>	.....	3
.....	.....	3
.....	.....	3
.....	.....	4



# JBoss EAP 7 parameter size

```
INFO [stdout] (default task-5) javax.servlet.ServletException: UT000047:  
The number of parameters exceeded the maximum of 1000  
...  
INFO [stdout] (default task-5) Caused by: java.lang.IllegalStateException:  
UT000047: The number of parameters exceeded the maximum of 1000  
INFO [stdout] (default task-5)         at  
io.undertow.server.handlers.form.FormData.add(FormData.java:78)  
INFO [stdout] (default task-5)         at  
io.undertow.server.handlers.form.FormData.add(FormData.java:68)  
INFO [stdout] (default task-5)         at  
io.undertow.server.handlers.form.FormEncodedDataDefinition$FormEncodedDataPa  
rser.doParse/FormEncodedDataDefinition.java:172)  
INFO [stdout] (default task-5)         at  
io.undertow.server.handlers.form.FormEncodedDataDefinition$FormEncodedDataPa  
rser.parseBlocking/FormEncodedDataDefinition.java:251)  
INFO [stdout] (default task-5)         at  
io.undertow.servlet.spec.HttpServletRequestImpl.parseFormData(HttpServletReq  
uestImpl.java:762)  
INFO [stdout] (default task-5)         at  
io.undertow.servlet.spec.HttpServletRequestImpl.getParameter(HttpServletRequ  
estImpl.java:636)  
INFO [stdout] (default task-5)         at  
javax.servlet.ServletRequestWrapper.getParameter(ServletRequestWrapper.java:  
194)  
...  
The number of parameters exceeded the maximum of 1000      가  
POST/GET          가          가  
1000           1000  가    가          가
```

http-listener, ajp-listener, https-listener                    max-parameters

jboss-cli

```
[standalone@localhost:9999 /] /subsystem=undertow/server=default-  
server/http-listener=default/:write-attribute(name=max-  
parameters,value=5000)
```

## xml

```
<subsystem xmlns="urn:jboss:domain:undertow:3.1">
    <buffer-cache name="default"/>
    <server name="default-server">
        <http-listener name="default" max-parameters="2000" socket-
binding="http" redirect-socket="https"/>
        <host name="default-host" alias="localhost">
            ... (snip) ..
        </host>
    </server>
    ... (snip) ..
```

max-parameters	Integer.MAX_VALUE	가
.	DDOS	.

- <https://access.redhat.com/solutions/2973611>

From:  
<https://atl.kr/dokuwiki/> - AllThatLinux!



Permanent link:  
[https://atl.kr/dokuwiki/doku.php/jboss\\_eap\\_7\\_parameter\\_size\\_%EB%B3%80%EA%B2%BD](https://atl.kr/dokuwiki/doku.php/jboss_eap_7_parameter_size_%EB%B3%80%EA%B2%BD)

Last update: **2023/01/09 08:14**