

JBoss EAP 7 parameter size 3

..... 3

..... 3

..... 4

JBoss EAP 7 parameter size

```

INFO [stdout] (default task-5) javax.servlet.ServletException: UT000047:
The number of parameters exceeded the maximum of 1000
...
INFO [stdout] (default task-5) Caused by: java.lang.IllegalStateException:
UT000047: The number of parameters exceeded the maximum of 1000
INFO [stdout] (default task-5)         at
io.undertow.server.handlers.form.FormData.add(FormData.java:78)
INFO [stdout] (default task-5)         at
io.undertow.server.handlers.form.FormData.add(FormData.java:68)
INFO [stdout] (default task-5)         at
io.undertow.server.handlers.form.FormEncodedDataDefinition$FormEncodedDataPa
rser.doParse(FormEncodedDataDefinition.java:172)
INFO [stdout] (default task-5)         at
io.undertow.server.handlers.form.FormEncodedDataDefinition$FormEncodedDataPa
rser.parseBlocking(FormEncodedDataDefinition.java:251)
INFO [stdout] (default task-5)         at
io.undertow.servlet.spec.HttpServletRequestImpl.parseFormData(HttpServletRequestReq
uestImpl.java:762)
INFO [stdout] (default task-5)         at
io.undertow.servlet.spec.HttpServletRequestImpl.getParameter(HttpServletRequestRequ
estImpl.java:636)
INFO [stdout] (default task-5)         at
javax.servlet.ServletRequestWrapper.getParameter(ServletRequestWrapper.java:
194)
...

```

The number of parameters exceeded the maximum of 1000 가
 POST/GET 가 가 가 .
 1000 1000 가 가 가 .

http-listener, ajp-listener, https-listener max-parameters

jboss-cli

```

[standalone@localhost:9999 /] /subsystem=undertow/server=default-
server/http-listener=default/:write-attribute(name=max-
parameters,value=5000)

```

xml

```
<subsystem xmlns="urn:jboss:domain:undertow:3.1">
  <buffer-cache name="default"/>
  <server name="default-server">
    <http-listener name="default" max-parameters="2000" socket-binding="http" redirect-socket="https"/>
    <host name="default-host" alias="localhost">
      ...(snip)..
    </host>
  </server>
  ...(snip)..
</subsystem>
```

max-parameters Integer.MAX_VALUE 가
DDOS

- <https://access.redhat.com/solutions/2973611>

From: <https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://atl.kr/dokuwiki/doku.php/jboss_eap_7_parameter_size_%EB%B3%80%EA%B2%BD

Last update: 2023/01/09 08:14

