목차

rgmanager status lvm return 1 3
발생로그 3
문제해결 3

rgmanager status lvm return 1

발생로그

```
rgmanager[ ]: [lvm] Getting status
rgmanager[ ]: [lvm] WARNING : vg00 should not be active
rgmanager[ ]: [lvm] WARNING : node1 does not own vg00
rgmanager[ ]: [lvm] WARNING : Attempting shutdown of vg00
rgmanager[ ]: status on lvm "vg00" returned 1 (generic error)
```

문제해결

```
[root@localhost ~#]# lvs
/var/lock/lvm/v_vg00:aux: open failed: No space left on device
Can't get lock for VG00
```

위와 같은 메세지가 보일 경우 파일 시스템 용량 및 inode 가 full 난 경우를 의심 해야 한다. 파일 용량이 Full 이 아니여도 inode 가 Full 인 경우가 있음으로, 필히 확인해 봐야 한다.

```
[root@localhost ~]# df -ih
Filesystem           Inodes IUsed IFree IUse% Mounted on
/dev/mapper/VolGroup-lv_root
                       1.1M   97K  1.1M    9% /
tmpfs                  233K     5  233K    1% /dev/shm
/dev/sda1              126K    39  125K    1% /boot
/test                  1.1M   1.1M  0    100% /test
```

디스크 정리를 하면 해당 원인은 해결된다.

From:
https://atl.kr/dokuwiki/ - **AllThatLinux!**

Permanent link:
https://atl.kr/dokuwiki/doku.php/lvm_%EB%AC%B8%EC%A0%9C%EB%A1%9C_%EC%9D%B8%ED%95%9C_failover

Last update: **2016/02/01 04:48**