

PXE Server - UEFI

```
dnf install tftp-server dhcp-server  
firewall-cmd --add-service=tftp
```

dhcpd.conf

```
#  
# DHCP Server Configuration file.  
# see /usr/share/doc/dhcp-server/dhcpd.conf.example  
# see dhcpd.conf(5) man page  
#  
  
#option domain-name "local.domain";  
#option domain-name-servers dns.local.domain;  
default-lease-time 600;  
max-lease-time 7200;  
authoritative;  
# add follows  
option space pxelinux;  
option pxelinux.magic code 208 = string;  
option pxelinux.configfile code 209 = text;  
option pxelinux.pathprefix code 210 = text;  
option pxelinux.reboottime code 211 = unsigned integer 32;  
option architecture-type code 93 = unsigned integer 16;  
  
subnet 10.0.0.0 netmask 255.255.255.0 {  
    range dynamic-bootp 10.0.0.200 10.0.0.254;  
    option broadcast-address 10.0.0.255;  
    option routers 10.0.0.1;  
    # add follows  
    class "pxeclients" {  
        match if substring (option vendor-class-identifier, 0, 9) =  
"PXEClient";  
  
        # PXE servers hostname or IP address  
        next-server 10.0.0.9;  
  
        if option architecture-type = 00:07 {  
            filename "BOOTX64.EFI";  
        }  
        else {  
            filename "pxelinux.0";  
        }  
    }  
}
```

/var/lib/tftpboot/grub.cfg

```
set default="1"

function load_video {
    insmod efi_gop
    insmod efi_uga
    insmod video_bochs
    insmod video_cirrus
    insmod all_video
}

load_video
set gfxpayload=keep
insmod gzio
insmod part_gpt
insmod ext2

#insmod gfxterm
#terminal_output gfxterm
#loadfont /EFI/BOOT/fonts/unicode.pf2
#insmod gfxterm_background
#insmod png
#background_image -m stretch /EFI/BOOT/splash.png

set timeout=60

### CentOS ###
submenu 'CentOS' {
    configfile CentOS/CentOS.menu.efi
}

#submenu 'CentOS' {
#    menuentry 'Install CentOS 7' --class fedora --class gnu-linux --class
gnu --class os {
#        linuxefi /CentOS/7/isolinux/vmlinuz
inst.repo=http://10.0.0.9/media/CentOS7
#        initrdefi /CentOS/7/isolinux/initrd.img
#    }
#}

### RHEL ###
submenu 'RHEL' {
    configfile RHEL/RHEL.menu.efi
}
```

CentOS.menu.efi

```
menuentry 'Install CentOS 7' --class fedora --class gnu-linux --class gnu --  
class os {  
    linuxefi /CentOS/7/isolinux/vmlinuz  
    inst.repo=http://10.0.0.9/media/CentOS7  
    initrdefi /CentOS/7/isolinux/initrd.img  
}
```

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

https://atl.kr/dokuwiki/doku.php/pxe_server_-_uefi?rev=1729139293

Last update: **2024/10/17 04:28**

