

- RHEV 3.6 Backup / Restore** 3
 - 3
 - 3
 - 3
- script** 3
 - DB Corruption** 5
 - Memory Size** 6

RHEV 3.6 Backup / Restore

— 2016/04/16 01:10

```
Self-Hosted Engine      Maintenance mode      .
Self Host                Manager VM  maintenance      .
```

```
hosted-engine --set-maintenance --mode=global
```

Manager

```
[root@host]# engine-backup --scope=all --mode=backup --file=BACKUP_FILE --
log=LOG_FILE
```

```
[root@host]# service ovirt-engine stop
```

```
[root@host]# engine-cleanup
```

```
[root@host]# su - postgres -c psql
alter role engine encrypted password 'PASSWORD';
```

```
[root@host]# engine-backup --mode=restore --scope=all --file=BACKUP_FILE --
log=LOG_FILE --change-db-credentials --db-host=localhost --db-name=engine --
db-user=engine --db-password --restore-permissions
```

```
[root@host]# engine-setup
```

script

```
#!/bin/bash
# Usage : restore.sh DB_PASS RESTORE_FILE
#

if [ $# -ne 2 ]
then
    echo "Usage : restore.sh <DB_PASS> <RESTORE_FILE>";
    exit 1;
fi

PASSWORD=$1
RESTORE_FILE=$2

##### check daemon
echo "check ovirt-engine daemon..."
service ovirt-engine status
if [ $? -ne 3 ]
then
    echo "Service ovirt-engine is not stopped.";
    echo "Service ovirt-engine daemon MUST stop.";
    echo "Exit";
    exit 1;
fi

engine-cleanup << EOF
yes
ok
ok
EOF

if [ $? -ne 0 ]
then
    echo "engine-cleanup is not completed";
    echo "Exit";
    exit 1;
fi

su - postgres -c psql << EOF
alter role engine encrypted password '$PASSWORD';
\q
EOF

if [ $? -ne 0 ]
then
    echo "db password is not set";
    echo "Exit";
    exit 1;
fi

engine-backup --mode=restore --scope=all --file=$RESTORE_FILE --
log=restore.log --change-db-credentials --db-host=localhost --db-name=engine
```

```
--db-user=engine --db-password=$PASSWORD --restore-permissions

engine-setup << EOF
yes
no
ok
EOF

echo "Restore Done"
```

- DB Corruption

가 engine-cleanup engine-setup 가 database가
 . psql 가 database list .

```
[root@host2 ~]# su - postgres -c psql
psql (8.4.20)
Type "help" for help.
```

```
postgres=# \l
                                List of databases
  Name            | Owner          | Encoding | Collation |
-----+-----+-----+-----+
 engine_20160416011028 | engine_20160416011028 | UTF8     | en_US.UTF-8 |
 en_US.UTF-8 |
 engine_20160416011808 | engine_20160416011808 | UTF8     | en_US.UTF-8 |
 en_US.UTF-8 |
 postgres          | postgres       | UTF8     | en_US.UTF-8 |
 en_US.UTF-8 |
 template0         | postgres       | UTF8     | en_US.UTF-8 |
 en_US.UTF-8 | =c/postgres
: postgres=CTc/postgres
 template1         | postgres       | UTF8     | en_US.UTF-8 |
 en_US.UTF-8 | =c/postgres
: postgres=CTc/postgres
(5 rows)
```

```
postgres=# drop database engine_20160416011028;
DROP DATABASE
postgres=# drop database engine_20160416011808;
DROP DATABASE
postgres=# \l
```

```
                                List of databases
  Name            | Owner          | Encoding | Collation |
-----+-----+-----+-----+
  Name            | Owner          | Encoding | Collation |
-----+-----+-----+-----+
                                Ctype          | Access
privileges
```

```

-----
postgres | postgres | UTF8      | en_US.UTF-8 | en_US.UTF-8 |
template0 | postgres | UTF8      | en_US.UTF-8 | en_US.UTF-8 | =c/postgres
:
postgres=CtC/postgres
template1 | postgres | UTF8      | en_US.UTF-8 | en_US.UTF-8 | =c/postgres
:
postgres=CtC/postgres
(3 rows)

postgres=# \q

```

- Memory Size

```

가 . 가 가
engine-setup 가 /var/log/messages 가 .

```

```

Apr 21 17:02:53 testvm002 2016-04-21 17:02:53,974 ovirt-engine: ERROR
run:532 Error: Cannot detect JBoss version

```

engine-setup

```

ENGINE_HEAP_MIN="4096M" #
ENGINE_HEAP_MAX="4096M"

```

oVirt

8GB	1964M
32GB	7959M
256GB	64565M

From: <https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://atl.kr/dokuwiki/doku.php/rhev_3.6_backup_restore?rev=1486545398

Last update: 2017/02/08 09:16

