

- RHEV 3.6 hosted-engine gateway** ..... 3
- ..... 3
- Put the cluster in global maintenance. .... 3
- Stop the HA services on all hosts: ..... 3
- hosted-engine 가 ..... 3
- ..... 3
- Start the HA services on all hosts: ..... 4
- Disable global Maintenance: ..... 4
- ..... 4



# RHEV 3.6 hosted-engine gateway

: RHEV 3.6

gateway

## Put the cluster in global maintenance.

```
# hosted-engine --set-maintenance --mode=global
```

## Stop the HA services on all hosts:

```
# systemctl stop ovirt-ha-agent.service  
# systemctl stop ovirt-ha-broker.service
```

## hosted-engine

가

```
# dir=`mktemp -d` && cd $dir  
# sdUUID_line=$(grep sdUUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# sdUUID=${sdUUID_line:7:36}  
# conf_volume_UUID_line=$(grep conf_volume_UUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# conf_volume_UUID=${conf_volume_UUID_line:17:36}  
# conf_image_UUID_line=$(grep conf_image_UUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# conf_image_UUID=${conf_image_UUID_line:16:36}  
# dd if=/rhev/data-center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID  
2>/dev/null| tar -xvf -  
  
# hosted-engine 가 .  
# fhanswers.conf answers  
  
# cp /etc/ovirt-hosted-engine/answers.conf.rpmsave fhanswers.conf # or edit  
answers.conf as you need.
```

Last update: rhev\_3.6\_hosted-engine\_gateway\_ - [https://at1.kr/dokuwiki/doku.php/rhev\\_3.6\\_hosted-engine\\_gateway\\_%EB%B3%80%EA%B2%BD](https://at1.kr/dokuwiki/doku.php/rhev_3.6_hosted-engine_gateway_%EB%B3%80%EA%B2%BD)  
2019/09/05 06:12

---

```
# tar -c0 * | dd of=/rhev/data-center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID
```

## Start the HA services on all hosts:

```
# systemctl start ovirt-ha-broker.service  
# systemctl start ovirt-ha-agent.service
```

## Disable global Maintenance:

```
# hosted-engine --set-maintenance --mode=none
```

- <https://access.redhat.com/solutions/2348341>

From:  
<https://at1.kr/dokuwiki/> - AllThatLinux!

Permanent link:  
[https://at1.kr/dokuwiki/doku.php/rhev\\_3.6\\_hosted-engine\\_gateway\\_%EB%B3%80%EA%B2%BD](https://at1.kr/dokuwiki/doku.php/rhev_3.6_hosted-engine_gateway_%EB%B3%80%EA%B2%BD)

Last update: **2019/09/05 06:12**

