

**WAS**

- ..... 3
- ..... 3
- ..... 3
- ..... 3
- ..... 5

was\_  
Last  
update: - [https://atl.kr/dokuwiki/doku.php/was\\_%EB%B3%B4%EC%95%88\\_%EC%B7%A8%EC%95%BD%EC%A0%90\\_%EC%A0%90%EA%B2%80?rev=1528093960](https://atl.kr/dokuwiki/doku.php/was_%EB%B3%B4%EC%95%88_%EC%B7%A8%EC%95%BD%EC%A0%90_%EC%A0%90%EA%B2%80?rev=1528093960)  
2018/06/04  
06:32 -

---

# WAS

## Tomcat

server.xml connector xpoweredBy, server 가 .

```
<Connector port="8080" protocol="HTTP/1.1"
  connectionTimeout="20000"
  redirectPort="8443"
  xpoweredBy="foo"
  server="bar"
/>
```

## JBoss EAP 6.x

- SERVER

SERVER org.apache.coyote.http11.Http11Protocol.SERVER Property 가 .

```
org.apache.coyote.http11.Http11Protocol.SERVER="foo"
```

```
<system-properties>
  <property name="org.apache.coyote.http11.Http11Protocol.SERVER"
value="foo"/>
</system-properties>
```

- X-PoweredBy

X-PoweredBy JBoss .

```
/subsystem=web/configuration=jsp-configuration/:write-attribute(name=x-
powered-by,value=false)
{
  "outcome" => "success",
  "response-headers" => {
    "operation-requires-reload" => true,
    "process-state" => "reload-required"
  }
}
```

가 .

```
<subsystem xmlns="urn:jboss:domain:web:1.1" default-virtual-server="default-
host" native="false">
  <configuration>
    <jsp-configuration x-powered-by="false"/>
  </configuration>
  ...
  ...
</subsystem>
```

## JBoss EAP 7.x

- Server: JBoss-EAP/7 X-Powered-By: Undertow/1

CLI

```
/subsystem=undertow/server=default-server/host=default-host/filter-ref=x-
powered-by-header:remove
/subsystem=undertow/server=default-server/host=default-host/filter-
ref=server-header:remove
```

CLI

```
/subsystem=undertow/configuration=filter/response-header=server-
header:write-attribute(name=header-value,value=foo)
/subsystem=undertow/configuration=filter/response-header=x-powered-by-
header:write-attribute(name=header-value,value=bar)
```

- X-Powered-By: JSP/2.3

## CLI

```
/subsystem=undertow/servlet-container=default/setting=jsp:write-attribute(name=x-powered-by,value=false)
```

- <https://access.redhat.com/solutions/21075>
- <https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html#Connectors>

From:  
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:  
[https://atl.kr/dokuwiki/doku.php/was\\_%EB%B3%B4%EC%95%88\\_%EC%B7%A8%EC%95%BD%EC%A0%90\\_%EC%A0%90%EA%B2%80?rev=1528093960](https://atl.kr/dokuwiki/doku.php/was_%EB%B3%B4%EC%95%88_%EC%B7%A8%EC%95%BD%EC%A0%90_%EC%A0%90%EA%B2%80?rev=1528093960)

Last update: **2018/06/04 06:32**

