

/etc/kolla/globals.yml

3

globals.yml configuration

3

/etc/kolla/globals.yml

kolla-ansible

가

https://github.com/openstack/kolla-ansible/blob/master/ansible/group_vars/all.yml

kolla-ansible

가 /root/venv/share/kolla-ansible/ansible/group_vars/all.yml

OS /usr/local/share/kolla-ansible/ansible/group_vars/all.yml

globals.yml configuration

<https://github.com/openstack/kolla-ansible/blob/master/etc/kolla/globals.yml>

```
---
# You can use this file to override _any_ variable throughout Kolla.
# Additional options can be found in the
# 'kolla-ansible/ansible/group_vars/all.yml' file. Default value of all the
# commented parameters are shown here, To override the default value
# uncomment
# the parameter and change its value.

#####
# Ansible options
#####

# This variable is used as the "filter" argument for the setup module. For
# instance, if one wants to remove/ignore all Neutron interface facts:
# kolla_ansible_setup_filter: "ansible[!qt]*"
# By default, we do not provide a filter.
#kolla_ansible_setup_filter: "{{ omit }}"

# This variable is used as the "gather_subset" argument for the setup
# module.
# For instance, if one wants to avoid collecting facts via facter:
# kolla_ansible_setup_gather_subset: "all,!facter"
# By default, we do not provide a gather subset.
#kolla_ansible_setup_gather_subset: "{{ omit }}"

# Dummy variable to allow Ansible to accept this file.
```

workaround_ansible_issue_8743: yes

This variable is used as "any_errors_fatal" setting for the setup (gather facts) plays.

This is useful for weeding out failing hosts early to avoid late failures due to missing facts (especially cross-host).

Do note this still supports host fact caching and it will not affect scenarios with all facts cached (as there is no task to fail).

#kolla_ansible_setup_any_errors_fatal: false

This variable may be used to set the maximum failure percentage for all plays. More fine-grained control is possible via per-service variables, e.g.

nova_max_fail_percentage. The default behaviour is to set a max fail percentage of 100, which is equivalent to not setting it.

#kolla_max_fail_percentage:

#####

Kolla options

#####

Valid options are [COPY_ONCE, COPY_ALWAYS]

#config_strategy: "COPY_ALWAYS"

Valid options are ['centos', 'debian', 'rocky', 'ubuntu']

#kolla_base_distro: "rocky"

Do not override this unless you know what you are doing.

#openstack_release: "master"

Docker image tag used by default.

#openstack_tag: "{{ openstack_release ~ openstack_tag_suffix }}"

Suffix applied to openstack_release to generate openstack_tag.

#openstack_tag_suffix: ""

Location of configuration overrides

#node_custom_config: "{{ node_config }}/config"

This should be a VIP, an unused IP on your network that will float between the hosts running keepalived for high-availability. If you want to run an All-In-One without haproxy and keepalived, you can set enable_haproxy to no

in "OpenStack options" section, and set this value to the IP of your 'network_interface' as set in the Networking section below.

#kolla_internal_vip_address: "10.10.10.254"

This is the DNS name that maps to the kolla_internal_vip_address VIP. By default it is the same as kolla_internal_vip_address.

#kolla_internal_fqdn: "{{ kolla_internal_vip_address }}"

This should be a VIP, an unused IP on your network that will float between

```
# the hosts running keepalived for high-availability. It defaults to the
# kolla_internal_vip_address, allowing internal and external communication
to
# share the same address. Specify a kolla_external_vip_address to separate
# internal and external requests between two VIPs.
#kolla_external_vip_address: "{{ kolla_internal_vip_address }}"

# The Public address used to communicate with OpenStack as set in the
public_url
# for the endpoints that will be created. This DNS name should map to
# kolla_external_vip_address.
#kolla_external_fqdn: "{{ kolla_external_vip_address }}"

# Optionally change the path to sysctl.conf modified by Kolla Ansible plays.
#kolla_sysctl_conf_path: /etc/sysctl.conf

#####
# Container engine
#####

# Valid options are [ docker, podman ]
#kolla_container_engine: docker

#####
# Docker options
#####

# Custom docker registry settings:
#docker_registry:
# Please read the docs carefully before applying docker_registry_insecure.
#docker_registry_insecure: "no"
#docker_registry_username:
# docker_registry_password is set in the passwords.yml file.

# Namespace of images:
#docker_namespace: "kolla"

# Docker client timeout in seconds.
#docker_client_timeout: 120

#docker_configure_for_zun: "no"
#containerd_configure_for_zun: "no"
#containerd_grpc_gid: 42463

#####
# Messaging options
#####
# Whether to enable TLS for oslo.messaging communication with RabbitMQ.
#om_enable_rabbitmq_tls: "{{ rabbitmq_enable_tls | bool }}"
# CA certificate bundle in containers using oslo.messaging with RabbitMQ
```

```
TLS.
#om_rabbitmq_cacert: "{{ rabbitmq_cacert }}"

#####
# Neutron - Networking Options
#####
# This interface is what all your api services will be bound to by default.
# Additionally, all vxlan/tunnel and storage network traffic will go over
this
# interface by default. This interface must contain an IP address.
# It is possible for hosts to have non-matching names of interfaces - these
can
# be set in an inventory file per host or per group or stored separately,
see
# http://docs.ansible.com/ansible/latest/intro\_inventory.html
# Yet another way to workaround the naming problem is to create a bond for
the
# interface on all hosts and give the bond name here. Similar strategy can
be
# followed for other types of interfaces.
#network_interface: "eth0"

# These can be adjusted for even more customization. The default is the same
as
# the 'network_interface'. These interfaces must contain an IP address.
#kolla_external_vip_interface: "{{ network_interface }}"
#api_interface: "{{ network_interface }}"
#swift_storage_interface: "{{ network_interface }}"
#swift_replication_interface: "{{ swift_storage_interface }}"
#tunnel_interface: "{{ network_interface }}"
#dns_interface: "{{ network_interface }}"
#octavia_network_interface: "{{ api_interface }}"

# Configure the address family (AF) per network.
# Valid options are [ ipv4, ipv6 ]
#network_address_family: "ipv4"
#api_address_family: "{{ network_address_family }}"
#storage_address_family: "{{ network_address_family }}"
#swift_storage_address_family: "{{ storage_address_family }}"
#swift_replication_address_family: "{{ swift_storage_address_family }}"
#migration_address_family: "{{ api_address_family }}"
#tunnel_address_family: "{{ network_address_family }}"
#octavia_network_address_family: "{{ api_address_family }}"
#bifrost_network_address_family: "{{ network_address_family }}"
#dns_address_family: "{{ network_address_family }}"

# This is the raw interface given to neutron as its external network port.
Even
# though an IP address can exist on this interface, it will be unusable in
most
# configurations. It is recommended this interface not be configured with
```

```
any IP
# addresses for that reason.
#neutron_external_interface: "eth1"

# Valid options are [ openvswitch, ovn, linuxbridge, vmware_nsxv,
vmware_nsxv3, vmware_nsxp, vmware_dvs ]
# if vmware_nsxv3 or vmware_nsxp is selected, enable_openvswitch MUST be set
to "no" (default is yes)
# Do note linuxbridge is *EXPERIMENTAL* in Neutron since Zed and it requires
extra tweaks to config to be usable.
# For details, see:
https://docs.openstack.org/neutron/latest/admin/config-experimental-framework.html
#neutron_plugin_agent: "openvswitch"

# Valid options are [ internal, infoblox ]
#neutron_ipam_driver: "internal"

# Configure Neutron upgrade option, currently Kolla support
# two upgrade ways for Neutron: legacy_upgrade and rolling_upgrade
# The variable "neutron_enable_rolling_upgrade: yes" is meaning
rolling_upgrade
# were enabled and opposite
# Neutron rolling upgrade were enable by default
#neutron_enable_rolling_upgrade: "yes"

# Configure neutron logging framework to log ingress/egress connections to
instances
# for security groups rules. More information can be found here:
# https://docs.openstack.org/neutron/latest/admin/config-logging.html
#enable_neutron_packet_logging: "no"

#####
# keepalived options
#####
# Arbitrary unique number from 0..255
# This should be changed from the default in the event of a multi-region
deployment
# where the VIPs of different regions reside on a common subnet.
#keepalived_virtual_router_id: "51"

#####
# Dimension options
#####
# This is to provide an extra option to deploy containers with Resource
constraints.
# We call it dimensions here.
# The dimensions for each container are defined by a mapping, where each
dimension value should be a
# string.
# Reference_Docs
```

```
# https://docs.docker.com/config/containers/resource_constraints/
# eg:
# <container_name>_dimensions:
#   blkio_weight:
#   cpu_period:
#   cpu_quota:
#   cpu_shares:
#   cpuset_cpus:
#   cpuset_mems:
#   mem_limit:
#   mem_reservation:
#   memswap_limit:
#   kernel_memory:
#   ulimits:

#####
# Healthcheck options
#####
#enable_container_healthchecks: "yes"
# Healthcheck options for Docker containers
# interval/timeout/start_period are in seconds
#default_container_healthcheck_interval: 30
#default_container_healthcheck_timeout: 30
#default_container_healthcheck_retries: 3
#default_container_healthcheck_start_period: 5

#####
# Firewall options
#####
# Configures firewalld on both ubuntu and centos systems
# for enabled services.
# firewalld should be installed beforehand.
# disable_firewall: "true"
# enable_external_api_firewalld: "false"
# external_api_firewalld_zone: "public"

#####
# TLS options
#####
# To provide encryption and authentication on the
kolla_external_vip_interface,
# TLS can be enabled. When TLS is enabled, certificates must be provided to
# allow clients to perform authentication.
#kolla_enable_tls_internal: "no"
#kolla_enable_tls_external: "{{ kolla_enable_tls_internal if
kolla_same_external_internal_vip | bool else 'no' }}"
#kolla_certificates_dir: "{{ node_config }}/certificates"
#kolla_external_fqdn_cert: "{{ kolla_certificates_dir }}/haproxy.pem"
#kolla_internal_fqdn_cert: "{{ kolla_certificates_dir }}/haproxy-
internal.pem"
#kolla_admin_openrc_cacert: ""
```

```
#kolla_copy_ca_into_containers: "no"
#haproxy_backend_cacert: "{{ 'ca-certificates.crt' if kolla_base_distro in
['debian', 'ubuntu'] else 'ca-bundle.trust.crt' }}"
#haproxy_backend_cacert_dir: "/etc/ssl/certs"

#####
# Backend options
#####
#kolla_httpd_keep_alive: "60"
#kolla_httpd_timeout: "60"

#####
# Backend TLS options
#####
#kolla_enable_tls_backend: "no"
#kolla_verify_tls_backend: "yes"
#kolla_tls_backend_cert: "{{ kolla_certificates_dir }}/backend-cert.pem"
#kolla_tls_backend_key: "{{ kolla_certificates_dir }}/backend-key.pem"

#####
# ACME client options
#####
# A list of haproxy backend server directives pointing to addresses used by
the
# ACME client to complete http-01 challenge.
# Please read the docs for more details.
#acme_client_servers: []

#####
# LetsEncrypt options
#####
# This option is required for letsencrypt role to work properly.
#letsencrypt_email: ""

#####
# LetsEncrypt certificate server options
#####
#letsencrypt_cert_server: "https://acme-v02.api.letsencrypt.org/directory"
# attempt to renew Let's Encrypt certificate every 12 hours
#letsencrypt_cron_renew_schedule: "0 */12 * * *"

#####
# Region options
#####
# Use this option to change the name of this region.
#openstack_region_name: "RegionOne"

# Use this option to define a list of region names - only needs to be
configured
# in a multi-region deployment, and then only in the *first* region.
#multiple_regions_names: ["{{ openstack_region_name }}"]
```

```
#####
# OpenStack options
#####
# Use these options to set the various log levels across all OpenStack
projects
# Valid options are [ True, False ]
#openstack_logging_debug: "False"

# Enable core OpenStack services. This includes:
# glance, keystone, neutron, nova, heat, and horizon.
#enable_openstack_core: "yes"

# These roles are required for Kolla to be operation, however a savvy
deployer
# could disable some of these required roles and run their own services.
#enable_glance: "{{ enable_openstack_core | bool }}"
#enable_hacluster: "no"
#enable_haproxy: "yes"
#enable_keepalived: "{{ enable_haproxy | bool }}"
#enable_keystone: "{{ enable_openstack_core | bool }}"
#enable_mariadb: "yes"
#enable_memcached: "yes"
#enable_neutron: "{{ enable_openstack_core | bool }}"
#enable_nova: "{{ enable_openstack_core | bool }}"
#enable_rabbitmq: "{{ 'yes' if om_rpc_transport == 'rabbit' or
om_notify_transport == 'rabbit' else 'no' }}"

# OpenStack services can be enabled or disabled with these options
#enable_aodh: "no"
#enable_barbican: "no"
#enable_blazar: "no"
#enable_ceilometer: "no"
#enable_ceilometer_ipmi: "no"
#enable_cells: "no"
#enable_central_logging: "no"
#enable_ceph_rgw: "no"
#enable_ceph_rgw_loadbalancer: "{{ enable_ceph_rgw | bool }}"
#enable_cinder: "no"
#enable_cinder_backup: "yes"
#enable_cinder_backend_hnas_nfs: "no"
#enable_cinder_backend_iscsi: "{{ enable_cinder_backend_lvm | bool }}"
#enable_cinder_backend_lvm: "no"
#enable_cinder_backend_nfs: "no"
#enable_cinder_backend_quobyte: "no"
#enable_cinder_backend_pure_iscsi: "no"
#enable_cinder_backend_pure_fc: "no"
#enable_cinder_backend_pure_roce: "no"
#enable_cloudkitty: "no"
#enable_collectd: "no"
#enable_cyborg: "no"
#enable_designate: "no"
```

```
#enable_destroy_images: "no"
#enable_etcd: "no"
#enable_fluentd: "yes"
#enable_fluentd_systemd: "{{ (enable_fluentd | bool) and
(enable_central_logging | bool) }}"
#enable_gnocchi: "no"
#enable_gnocchi_statsd: "no"
#enable_grafana: "no"
#enable_grafana_external: "{{ enable_grafana | bool }}"
#enable_heat: "{{ enable_openstack_core | bool }}"
#enable_horizon: "{{ enable_openstack_core | bool }}"
#enable_horizon_blazar: "{{ enable_blazar | bool }}"
#enable_horizon_cloudkitty: "{{ enable_cloudkitty | bool }}"
#enable_horizon_designate: "{{ enable_designate | bool }}"
#enable_horizon_fwaas: "{{ enable_neutron_fwaas | bool }}"
#enable_horizon_heat: "{{ enable_heat | bool }}"
#enable_horizon_ironic: "{{ enable_ironic | bool }}"
#enable_horizon_magnum: "{{ enable_magnum | bool }}"
#enable_horizon_manila: "{{ enable_manila | bool }}"
#enable_horizon_masakari: "{{ enable_masakari | bool }}"
#enable_horizon_mistral: "{{ enable_mistral | bool }}"
#enable_horizon_neutron_vpnaas: "{{ enable_neutron_vpnaas | bool }}"
#enable_horizon_octavia: "{{ enable_octavia | bool }}"
#enable_horizon_tacker: "{{ enable_tacker | bool }}"
#enable_horizon_trove: "{{ enable_trove | bool }}"
#enable_horizon_watcher: "{{ enable_watcher | bool }}"
#enable_horizon_zun: "{{ enable_zun | bool }}"
#enable_influxdb: "{{ enable_cloudkitty | bool and
cloudkitty_storage_backend == 'influxdb' }}"
#enable_ironic: "no"
#enable_ironic_neutron_agent: "{{ enable_neutron | bool and enable_ironic |
bool }}"
#enable_ironic_prometheus_exporter: "{{ enable_ironic | bool and
enable_prometheus | bool }}"
#enable_iscsid: "{{ enable_cinder | bool and enable_cinder_backend_iscsi |
bool }}"
#enable_kuryr: "no"
#enable_magnum: "no"
#enable_manila: "no"
#enable_manila_backend_generic: "no"
#enable_manila_backend_hnas: "no"
#enable_manila_backend_cephfs_native: "no"
#enable_manila_backend_cephfs_nfs: "no"
#enable_manila_backend_glusterfs_nfs: "no"
#enable_mariabackup: "no"
#enable_masakari: "no"
#enable_mistral: "no"
#enable_multipathd: "no"
#enable_neutron_vpnaas: "no"
#enable_neutron_sriov: "no"
#enable_neutron_dvr: "no"
```

```
#enable_neutron_fwaas: "no"
#enable_neutron_qos: "no"
#enable_neutron_agent_ha: "no"
#enable_neutron_bgp_dragent: "no"
#enable_neutron_provider_networks: "no"
#enable_neutron_segments: "no"
#enable_neutron_sfc: "no"
#enable_neutron_trunk: "no"
#enable_neutron_metering: "no"
#enable_neutron_infoblox_ipam_agent: "no"
#enable_neutron_port_forwarding: "no"
#enable_nova_serialconsole_proxy: "no"
#enable_nova_ssh: "yes"
#enable_octavia: "no"
#enable_octavia_driver_agent: "{{ enable_octavia | bool and
neutron_plugin_agent == 'ovn' }}"
#enable_octavia_jobboard: "{{ enable_octavia | bool and 'amphora' in
octavia_provider_drivers }}"
#enable_opensearch: "{{ enable_central_logging | bool or enable_osprofiler |
bool or (enable_cloudkitty | bool and cloudkitty_storage_backend ==
'opensearch') }}"
#enable_opensearch_dashboards: "{{ enable_opensearch | bool }}"
#enable_opensearch_dashboards_external: "{{ enable_opensearch_dashboards |
bool }}"
#enable_openvswitch: "{{ enable_neutron | bool and neutron_plugin_agent !=
'linuxbridge' }}"
#enable_ovn: "{{ enable_neutron | bool and neutron_plugin_agent == 'ovn' }}"
#enable_ovs_dpdk: "no"
#enable_osprofiler: "no"
#enable_placement: "{{ enable_nova | bool or enable_zun | bool }}"
#enable_prometheus: "no"
#enable_proxysql: "no"
#enable_redis: "no"
#enable_skyline: "no"
#enable_swift: "no"
#enable_swift_s3api: "no"
#enable_tacker: "no"
#enable_telegraf: "no"
#enable_trove: "no"
#enable_trove_singletenant: "no"
#enable_venus: "no"
#enable_watcher: "no"
#enable_zun: "no"

#####
# S3 options
#####
# Common options for S3 Cinder Backup and Glance S3 backend.
#s3_url:
#s3_bucket:
#s3_access_key:
```

```
#s3_secret_key:

#####
# RabbitMQ options
#####
# Options passed to RabbitMQ server startup script via the
# RABBITMQ_SERVER_ADDITIONAL_ERL_ARGS environment var.
# See Kolla Ansible docs RabbitMQ section for details.
# These are appended to args already provided by Kolla Ansible
# to configure IPv6 in RabbitMQ server.
# More details can be found in the RabbitMQ docs:
# https://www.rabbitmq.com/runtime.html#scheduling
# https://www.rabbitmq.com/runtime.html#busy-waiting
# The default tells RabbitMQ to always use two cores (+S 2:2),
# and not to busy wait (+sbwt none +sbwtdcpu none +sbwtdio none):
#rabbitmq_server_additional_erl_args: "+S 2:2 +sbwt none +sbwtdcpu none
+sbwtdio none"
# Whether to enable TLS encryption for RabbitMQ client-server communication.
#rabbitmq_enable_tls: "no"
# CA certificate bundle in RabbitMQ container.
#rabbitmq_cacert: "/etc/ssl/certs/{{ 'ca-certificates.crt' if
kolla_base_distro in ['debian', 'ubuntu'] else 'ca-bundle.trust.crt' }}"

#####
# MariaDB options
#####
# List of additional WSREP options
#mariadb_wsrep_extra_provider_options: []

#####
# External Ceph options
#####
# External Ceph - cephx auth enabled (this is the standard nowadays,
defaults to yes)
#external_ceph_cephx_enabled: "yes"

# Glance
#ceph_glance_user: "glance"
#ceph_glance_keyring: "client.{{ ceph_glance_user }}.keyring"
#ceph_glance_pool_name: "images"
# Cinder
#ceph_cinder_user: "cinder"
#ceph_cinder_keyring: "client.{{ ceph_cinder_user }}.keyring"
#ceph_cinder_pool_name: "volumes"
#ceph_cinder_backup_user: "cinder-backup"
#ceph_cinder_backup_keyring: "client.{{ ceph_cinder_backup_user }}.keyring"
#ceph_cinder_backup_pool_name: "backups"
# Nova
#ceph_nova_keyring: "{{ ceph_cinder_keyring }}"
#ceph_nova_user: "{{ ceph_cinder_user }}"
#ceph_nova_pool_name: "vms"
```

```
# Gnocchi
#ceph_gnocchi_user: "gnocchi"
#ceph_gnocchi_keyring: "client.{{ ceph_gnocchi_user }}.keyring"
#ceph_gnocchi_pool_name: "gnocchi"
# Manila
#ceph_manila_user: "manila"
#ceph_manila_keyring: "client.{{ ceph_manila_user }}.keyring"

#####
# Keystone - Identity Options
#####

#keystone_admin_user: "admin"

#keystone_admin_project: "admin"

# Interval to rotate fernet keys by (in seconds). Must be an interval of
# 60(1 min), 120(2 min), 180(3 min), 240(4 min), 300(5 min), 360(6 min),
# 600(10 min), 720(12 min), 900(15 min), 1200(20 min), 1800(30 min),
# 3600(1 hour), 7200(2 hour), 10800(3 hour), 14400(4 hour), 21600(6 hour),
# 28800(8 hour), 43200(12 hour), 86400(1 day), 604800(1 week).
#fernet_token_expiry: 86400

# Whether or not to apply changes to service user passwords when services
# are
# reconfigured
#update_keystone_service_user_passwords: "true"

#####
# Glance - Image Options
#####
# Configure image backend.
#glance_backend_ceph: "no"
#glance_backend_file: "yes"
#glance_backend_swift: "no"
#glance_backend_vmware: "no"
#glance_backend_s3: "no"
#enable_glance_image_cache: "no"
#glance_enable_property_protection: "no"
#glance_enable_interoperable_image_import: "no"
# Configure glance upgrade option.
# Due to this feature being experimental in glance,
# the default value is "no".
#glance_enable_rolling_upgrade: "no"

#####
# Glance S3 Backend
#####
#glance_backend_s3_url: "{{ s3_url }}"
#glance_backend_s3_bucket: "{{ s3_bucket }}"
#glance_backend_s3_access_key: "{{ s3_access_key }}"
```

```
#glance_backend_s3_secret_key: "{{ s3_secret_key }}"

#####
# Osprofiler options
#####
# valid values: ["elasticsearch", "redis"]
#osprofiler_backend: "elasticsearch"

#####
# Barbican options
#####
# Valid options are [ simple_crypto, pl1_crypto ]
#barbican_crypto_plugin: "simple_crypto"
#barbican_library_path: "/usr/lib/libCryptoki2_64.so"

#####
# Gnocchi options
#####
# Valid options are [ file, ceph, swift ]
#gnocchi_backend_storage: "{% if enable_swift | bool %}swift{% else %}file{%
endif %}"

# Valid options are [ redis, '' ]
#gnocchi_incoming_storage: "{{ 'redis' if enable_redis | bool else '' }}"

#####
# Cinder - Block Storage Options
#####
# Enable / disable Cinder backends
#cinder_backend_ceph: "no"
#cinder_backend_vmwarevc_vmdk: "no"
#cinder_backend_vmware_vstorage_object: "no"
#cinder_volume_group: "cinder-volumes"
# Valid options are [ '', redis, etcd ]
#cinder_coordination_backend: "{{ 'redis' if enable_redis|bool else 'etcd'
if enable_etcd|bool else '' }}"

# Valid options are [ nfs, swift, ceph, s3 ]
#cinder_backup_driver: "ceph"
#cinder_backup_share: ""
#cinder_backup_mount_options_nfs: ""

# Cinder backup S3 options
#cinder_backup_s3_url: "{{ s3_url }}"
#cinder_backup_s3_bucket: "{{ s3_bucket }}"
#cinder_backup_s3_access_key: "{{ s3_access_key }}"
#cinder_backup_s3_secret_key: "{{ s3_secret_key }}"

#####
# Cloudkitty options
#####
```

```
# Valid option is gnocchi
#cloudkitty_collector_backend: "gnocchi"
# Valid options are 'sqlalchemy' or 'influxdb'. The default value is
# 'influxdb', which matches the default in Cloudkitty since the Stein
release.
# When the backend is "influxdb", we also enable Influxdb.
# Also, when using 'influxdb' as the backend, we trigger the
configuration/use
# of Cloudkitty storage backend version 2.
#cloudkitty_storage_backend: "influxdb"

#####
# Designate options
#####
# Valid options are [ bind9 ]
#designate_backend: "bind9"
#designate_ns_record:
# - "ns1.example.org"
# Valid options are [ '', redis ]
#designate_coordination_backend: "{ 'redis' if enable_redis|bool else ''
}"

#####
# Nova - Compute Options
#####
#nova_backend_ceph: "no"

# Valid options are [ qemu, kvm, vmware ]
#nova_compute_virt_type: "kvm"

# The number of fake driver per compute node
#num_nova_fake_per_node: 5

# The flag "nova_safety_upgrade" need to be consider when
# "nova_enable_rolling_upgrade" is enabled. The "nova_safety_upgrade"
# controls whether the nova services are all stopped before rolling
# upgrade to the new version, for the safety and availability.
# If "nova_safety_upgrade" is "yes", that will stop all nova services
(except
# nova-compute) for no failed API operations before upgrade to the
# new version. And opposite.
#nova_safety_upgrade: "no"

# Valid options are [ none, novnc, spice ]
#nova_console: "novnc"

#####
# Neutron - networking options
#####
# Enable distributed floating ip for OVN deployments
#neutron_ovn_distributed_fip: "no"
```

```
# Enable DHCP agent(s) to use with OVN
#neutron_ovn_dhcp_agent: "no"

#####
# Horizon - Dashboard Options
#####
#horizon_backend_database: false

#####
# Ironic options
#####
# dnsmasq bind interface for Ironic Inspector, by default is
network_interface
#ironic_dnsmasq_interface: "{{ network_interface }}"
# The following value must be set when enabling ironic, the value format is
a
# list of ranges - at least one must be configured, for example:
# - range: 192.168.0.10,192.168.0.100
# See Kolla Ansible docs on Ironic for details.
#ironic_dnsmasq_dhcp_ranges:
# PXE bootloader file for Ironic Inspector, relative to
/var/lib/ironic/tftpboot.
#ironic_dnsmasq_boot_file: "pxelinux.0"

# Configure ironic upgrade option, due to currently kolla support
# two upgrade ways for ironic: legacy_upgrade and rolling_upgrade
# The variable "ironic_enable_rolling_upgrade: yes" is meaning
rolling_upgrade
# were enabled and opposite
# Rolling upgrade were enable by default
#ironic_enable_rolling_upgrade: "yes"

# List of extra kernel parameters passed to the kernel used during
inspection
#ironic_inspector_kernel_cmdline_extras: []

# Valid options are [ '', redis, etcd ]
#ironic_coordination_backend: "{{ 'redis' if enable_redis|bool else 'etcd'
if enable_etcd|bool else '' }}"

#####
# Manila - Shared File Systems Options
#####
# HNAS backend configuration
#hnas_ip:
#hnas_user:
#hnas_password:
#hnas_evs_id:
#hnas_evs_ip:
#hnas_file_system_name:
```

```
# CephFS backend configuration.
# External Ceph FS name.
# By default this is empty to allow Manila to auto-find the first FS
available.
#manila_cephfs_filesystem_name:

# Gluster backend configuration
# The option of glusterfs share layout can be directory or volume
# The default option of share layout is 'volume'
#manila_glusterfs_share_layout:
# The default option of nfs server type is 'Gluster'
#manila_glusterfs_nfs_server_type:

# Volume layout Options (required)
# If the glusterfs server requires remote ssh, then you need to fill
# in 'manila_glusterfs_servers', ssh user 'manila_glusterfs_ssh_user', and
ssh password
# 'manila_glusterfs_ssh_password'.
# 'manila_glusterfs_servers' value List of GlusterFS servers which provide
volumes,
# the format is for example:
#   - 10.0.1.1
#   - 10.0.1.2
#manila_glusterfs_servers:
#manila_glusterfs_ssh_user:
#manila_glusterfs_ssh_password:
# Used to filter GlusterFS volumes for share creation.
# Examples: manila-share-volume-\\d+$, manila-share-volume-#{size}G-\\d+$;
#manila_glusterfs_volume_pattern:

# Directory layout Options
# If the glusterfs server is on the local node of the manila share,
# it's of the format <glustervolserver>:/<glustervolid>
# If the glusterfs server is on a remote node,
# it's of the format <username>@<glustervolserver>:/<glustervolid> ,
# and define 'manila_glusterfs_ssh_password'
#manila_glusterfs_target:
#manila_glusterfs_mount_point_base:

#####
# Swift - Object Storage Options
#####
# Swift expects block devices to be available for storage. Two types of
storage
# are supported: 1 - storage device with a special partition name and
filesystem
# label, 2 - unpartitioned disk with a filesystem. The label of this
filesystem
# is used to detect the disk which Swift will be using.

# Swift support two matching modes, valid options are [ prefix, strict ]
```

```
#swift_devices_match_mode: "strict"

# This parameter defines matching pattern: if "strict" mode was selected,
# for swift_devices_match_mode then swift_device_name should specify the
name of
# the special swift partition for example: "KOLLA_SWIFT_DATA", if "prefix"
mode was
# selected then swift_devices_name should specify a pattern which would
match to
# filesystems' labels prepared for swift.
#swift_devices_name: "KOLLA_SWIFT_DATA"

# Configure swift upgrade option, due to currently kolla support
# two upgrade ways for swift: legacy_upgrade and rolling_upgrade
# The variable "swift_enable_rolling_upgrade: yes" is meaning
rolling_upgrade
# were enabled and opposite
# Rolling upgrade were enable by default
#swift_enable_rolling_upgrade: "yes"

#####
# VMware - OpenStack VMware support
#####
#vmware_vcenter_host_ip:
#vmware_vcenter_host_username:
#vmware_vcenter_host_password:
#vmware_datastore_name:
#vmware_vcenter_name:
#vmware_vcenter_cluster_name:

#####
# Prometheus
#####
#enable_prometheus_server: "{{ enable_prometheus | bool }}"
#enable_prometheus_haproxy_exporter: "{{ enable_haproxy | bool }}"
#enable_prometheus_mysqld_exporter: "{{ enable_mariadb | bool }}"
#enable_prometheus_node_exporter: "{{ enable_prometheus | bool }}"
#enable_prometheus_cadvisor: "{{ enable_prometheus | bool }}"
#enable_prometheus_fluentd_integration: "{{ enable_prometheus | bool and
enable fluentd | bool }}"
#enable_prometheus_memcached: "{{ enable_prometheus | bool }}"
#enable_prometheus_alertmanager: "{{ enable_prometheus | bool }}"
#enable_prometheus_alertmanager_external: "{{ enable_prometheus_alertmanager
| bool }}"
#enable_prometheus_ceph_mgr_exporter: "no"
#enable_prometheus_openstack_exporter: "{{ enable_prometheus | bool }}"
#enable_prometheus_elasticsearch_exporter: "{{ enable_prometheus | bool and
enable_elasticsearch | bool }}"
#enable_prometheus_blackbox_exporter: "{{ enable_prometheus | bool }}"
#enable_prometheus_libvirt_exporter: "{{ enable_prometheus | bool and
enable_nova | bool and nova_compute_virt_type in ['kvm', 'qemu'] }}"
```

```
#enable_prometheus_etcd_integration: "{{ enable_prometheus | bool and
enable_etcd | bool }}"
#enable_prometheus_msteams: "no"

# The labels to add to any time series or alerts when communicating with
external systems (federation, remote storage, Alertmanager).
# prometheus_external_labels:
#   <labelname>: <labelvalue>
# By default, prometheus_external_labels is empty
#prometheus_external_labels:

# List of extra parameters passed to prometheus. You can add as many to the
list.
#prometheus_cmdline_extras:

# List of extra parameters passed to cAdvisor. By default system cgroups
# and container labels are not exposed to reduce time series cardinality.
#prometheus_cadvisor_cmdline_extras: "--docker_only --
store_container_labels=false --
disable_metrics=percpu,referenced_memory,cpu_topology,resctrl,udp,advtcp,sch
ed,hugetlb,memory_numa,tcp,process"

# Extra parameters passed to Prometheus exporters.
#prometheus_blackbox_exporter_cmdline_extras:
#prometheus_elasticsearch_exporter_cmdline_extras:
#prometheus_memcached_exporter_cmdline_extras:
#prometheus_mysqld_exporter_cmdline_extras:
#prometheus_node_exporter_cmdline_extras:
#prometheus_openstack_exporter_cmdline_extras:

# Example of setting endpoints for prometheus ceph mgr exporter.
# You should add all ceph mgr's in your external ceph deployment.
#prometheus_ceph_mgr_exporter_endpoints:
#   - host1:port1
#   - host2:port2

#####
# Telegraf
#####
# Configure telegraf to use the docker daemon itself as an input for
# telemetry data.
#telegraf_enable_docker_input: "no"

#####
# Octavia - openstack loadbalancer Options
#####
# Whether to run Kolla Ansible's automatic configuration for Octavia.
# NOTE: if you upgrade from Ussuri, you must set `octavia_auto_configure` to
`no`
# and keep your other Octavia config like before.
#octavia_auto_configure: yes
```

```
# Octavia amphora flavor.
# See os_nova_flavor for details. Supported parameters:
# - flavorid (optional)
# - is_public (optional)
# - name
# - vcpus
# - ram
# - disk
# - ephemeral (optional)
# - swap (optional)
# - extra_specs (optional)
#octavia_amp_flavor:
#  name: "amphora"
#  is_public: no
#  vcpus: 1
#  ram: 1024
#  disk: 5

# Octavia security groups. lb-mgmt-sec-grp is for amphorae.
#octavia_amp_security_groups:
#  mgmt-sec-grp:
#    name: "lb-mgmt-sec-grp"
#    rules:
#      - protocol: icmp
#      - protocol: tcp
#        src_port: 22
#        dst_port: 22
#      - protocol: tcp
#        src_port: "{{ octavia_amp_listen_port }}"
#        dst_port: "{{ octavia_amp_listen_port }}"

# Octavia management network.
# See os_network and os_subnet for details. Supported parameters:
# - external (optional)
# - mtu (optional)
# - name
# - provider_network_type (optional)
# - provider_physical_network (optional)
# - provider_segmentation_id (optional)
# - shared (optional)
# - subnet
# The subnet parameter has the following supported parameters:
# - allocation_pool_start (optional)
# - allocation_pool_end (optional)
# - cidr
# - enable_dhcp (optional)
# - gateway_ip (optional)
# - name
# - no_gateway_ip (optional)
# - ip_version (optional)
# - ipv6_address_mode (optional)
```

```
# - ipv6_ra_mode (optional)
#octavia_amp_network:
#  name: lb-mgmt-net
#  shared: false
#  subnet:
#    name: lb-mgmt-subnet
#    cidr: "{{ octavia_amp_network_cidr }}"
#    no_gateway_ip: yes
#    enable_dhcp: yes

# Octavia management network subnet CIDR.
#octavia_amp_network_cidr: 10.1.0.0/24

#octavia_amp_image_tag: "amphora"

# Load balancer topology options are [ SINGLE, ACTIVE_STANDBY ]
#octavia_loadbalancer_topology: "SINGLE"

# The following variables are ignored as long as `octavia_auto_configure`
# is set to `yes`.
#octavia_amp_image_owner_id:
#octavia_amp_boot_network_list:
#octavia_amp_secgroup_list:
#octavia_amp_flavor_id:

#####
# Corosync options
#####

# this is UDP port
#hacluster_corosync_port: 5405

#####
# etcd options
#####
# If `etcd_remove_deleted_members` is enabled, Kolla Ansible will
# automatically
# remove etcd members from the cluster that are no longer in the inventory.
#etcd_remove_deleted_members: "no"
```

From:
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:
https://atl.kr/dokuwiki/doku.php/etc_kolla_globals.yml?rev=1722304582

Last update: **2024/07/30 01:56**

