

Apache Traffic Server ATS

Proxy

Configure

ATS

3

3

3

3

3

4

5

5

6



# Apache Traffic Server ATS

: <https://docs.trafficserver.apache.org/en/latest/admin-guide/introduction.en.html>

가 . IT 가 .

. 가 .

Traffic Server . Traffic Server 가

, ISP ( ),

## Proxy

remap.conf

```
CONFIG proxy.config.url_remap.remap_required INT 0
CONFIG proxy.config.reverse_proxy.enabled INT 0
```

Debian

```
# apt install trafficserver
```

- pkgconfig
- libtool
- gcc (>= 4.3 or clang > 3.0)
- GNU make
- openssl (libssl-dev for Ubuntu 16.04)
- pcre (libpcre3-dev for Ubuntu 16.04)
- libcap
- flex (for TPROXY)
- hwloc
- lua

- curses (for traffic\_top)
- curl (for traffic\_top)

GitHub

가

- git
- autoconf
- automake
- build-essential (for Ubuntu)
- libtool (for Ubuntu)

Git

```
autoreconf -if
```

## Configure

Traffic Server    configure  
                  Git

가

```
./configure --help
```

configure  
configure.ac가

```
./configure --prefix=/opt/ats
```

Traffic Server    nobody  
-with-user

```
./configure --prefix=/opt/ats --with-user=tserver
```

가            (/usr/local    /usr)

```
./configure --prefix=/opt/ats --with-lua=/opt/csw
```

configure            "INCLUDE\_PATH:LIBRARY\_PATH"

```
./configure --prefix=/opt/ats --with-  
pcre=/opt/csw/include:/opt/csw/lib/amd64
```

가

Makefile

.make check

```
make
make check
```

```
sudo make install
```

```
cd /opt/ats
sudo bin/traffic_server -R 1
```

## ATS

Traffic Server                      trafficserver start                      Traffic Server

```
bin/trafficserver start
```

```
traffic_ctl
```

```
traffic_ctl
```

```
bin/traffic_ctl COMMAND COMMAND ...
```

```
traffic_ctl
```

```
bin/traffic_ctl
```

```
trafficserver stop
```

```
(traffic_manager traffic_server)
가
```

```
bin/trafficserver stop
```

- apache\_traffic\_server\_-\_http\_proxy\_server\_on\_the\_edge\_presentation\_1.ppt

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

[https://atl.kr/dokuwiki/doku.php/apache\\_traffic\\_server?rev=1680951272](https://atl.kr/dokuwiki/doku.php/apache_traffic_server?rev=1680951272)

Last update: **2023/04/08 10:54**

