

Apache Traffic Server ATS 3

Proxy 3

 3

 3

 3

 3

Configure 4

ATS 5

 5

 6

Apache Traffic Server ATS

: <https://docs.trafficserver.apache.org/en/latest/admin-guide/introduction.en.html>

가 . IT 가 .

. 가 .

Traffic Server . Traffic Server 가 가

, ISP (),

Proxy

remap.conf

```
CONFIG proxy.config.url_remap.remap_required INT 0
CONFIG proxy.config.reverse_proxy.enabled INT 0
```

Debian .

```
# apt install trafficserver
```

- pkgconfig
- libtool
- gcc (>= 4.3 or clang > 3.0)
- GNU make
- openssl (libssl-dev for Ubuntu 16.04)
- pcre (libpcre3-dev for Ubuntu 16.04)
- libcap
- flex (for TPROXY)
- hwloc
- lua

- curses (for traffic_top)
- curl (for traffic_top)

GitHub 가

- git
- autoconf
- automake
- build-essential (for Ubuntu)
- libtool (for Ubuntu)

Git

```
autoreconf -if
```

Configure

Traffic Server configure Git 가

```
./configure --help
```

configure
configure.ac가

```
./configure --prefix=/opt/ats
```

```
Traffic Server nobody  
--with-user
```

```
./configure --prefix=/opt/ats --with-user=tserver
```

```
가 (/usr/local /usr)
```

```
./configure --prefix=/opt/ats --with-lua=/opt/csw
```

```
configure "INCLUDE_PATH:LIBRARY_PATH"
```

```
./configure --prefix=/opt/ats --with-  
pcre=/opt/csw/include:/opt/csw/lib/amd64
```

가

Makefile

.make check

```
make
make check
```

```
sudo make install
```

```
cd /opt/ats
sudo bin/traffic_server -R 1
```

ATS

Traffic Server Server trafficserver start Traffic Server

```
bin/trafficserver start
```

```
traffic_ctl
```

```
traffic_ctl
```

```
bin/traffic_ctl COMMAND COMMAND ...
```

```
traffic_ctl
```

```
bin/traffic_ctl
```

```
trafficserver stop
```

```
(traffic_manager traffic_server)
가
```

```
bin/trafficserver stop
```

- apache_traffic_server_-_http_proxy_server_on_the_edge_presentation_1.ppt

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

https://atl.kr/dokuwiki/doku.php/apache_traffic_server?rev=1680951272

Last update: **2023/04/08 10:54**

