

- Hosted Engine** 3
- RHEV-M*** 3
- /etc/ovirt-hosted-engine/vm.conf*** 3
- Hosted-engine*** 4
- 4

Hosted Engine

— 2016/03/31 10:34

: <https://access.redhat.com/articles/1248993>

: <https://access.redhat.com/solutions/964693>

RHEV-M

RHEV-M hosted engine

가

rhev-m vm

.

```
# hosted-engine --vm-status  
  
# hosted-engine --set-maintenance --mode=global  
  
# hosted-engine --vm-shutdown
```

/etc/ovirt-hosted-engine/vm.conf

.

```
vmId=10ed5831-959e-4c84-990a-64981aae8f67  
memSize=6144  
display=vnc  
devices={index:2,iface:ide,address:{ controller:0, target:0,unit:0, bus:1,  
type:drive},specParams:{},readonly:true,deviceId:b373338b-b519-49da-b5bc-  
dcfb84045293,path:/dev/cdrom,device:cdrom,shared:false,type:disk}  
devices={index:0,iface:virtio,format:raw,poolID:00000000-0000-0000-0000-0000  
00000000,volumeID:82483d62-62df-49d0-  
a87f-18cba1fa17a3,imageID:56ceaf8c-5d84-4387-  
a19d-9e767810faa6,specParams:{},readonly:false,domainID:476103ce-14aa-4a8c-9  
1d0-62d2bc5a45c6,optional:false,deviceId:56ceaf8c-5d84-4387-  
a19d-9e767810faa6,address:{bus:0x00, slot:0x06, domain:0x0000, type:pci,  
function:0x0},device:disk,shared:exclusive,propagateErrors:off,type:disk,boo  
tOrder:1}  
devices={device:scsi,model:virtio-scsi,type:controller}  
devices={nicModel:pv,macAddr:00:16:3e:2e:9a:ef,linkActive:true,network:rhev  
,filter:vdsm-no-mac-spoofing,specParams:{},deviceId:6c82762e-4475-474f-  
adca-514b36c9e1b0,address:{bus:0x00, slot:0x03, domain:0x0000, type:pci,  
function:0x0},device:bridge,type:interface}  
devices={device:console,specParams:{},type:console,deviceId:fc4590c1-  
e743-4ef1-b43d-8b6c3dfe2c4d,alias:console0}  
vmName=HostedEngine  
spiceSecureChannels=smain,sdisplay,sinputs,scursor,splayback,srecord,ssmartc  
ard,susbredir  
smp=4  
smpCoresPerSocket=4
```

```
smpThreadsPerCore=1  
cpuType=SandyBridge  
emulatedMachine=rhel6.5.0
```

: memSize CPU Cores : smp

Hosted-engine

```
# scp /etc/ovirt-hosted-engine/vm.conf root@hosted-engine-  
Host-02.example.com:/etc/ovirt-hosted-engine/vm.conf  
# scp /etc/ovirt-hosted-engine/vm.conf root@hosted-engine-  
Host-03.example.com:/etc/ovirt-hosted-engine/vm.conf
```

```
# hosted-engine --vm-start  
  
# hosted-engine --set-maintenance --mode=none
```

 3.6 VM
Global Maintenance
Global Maintenance WebUI

From: <https://at1.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://at1.kr/dokuwiki/doku.php/hosted_engine_change_spec_%EC%8A%A4%ED%8E%99_%EB%B3%80%EA%B2%BD%ED%95%98%EA%B8%B0

Last update: 2019/09/05 01:48

