

Openstack overcloud

..... 3

Openstack overcloud

가

가 가

```
# openstack stack failures list overcloud --long
```

#2

```
# heat resource-show overcloud Controller
resource_status CREATE_FAILED
# openstack stack resource list overcloud -c resource_name -c
resource_status | grep 'CREATE_FAILED'

#heat resource-list -n5 overcloud|grep -v COMPLE
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+
+-----+
| resource_name          | physical_resource_id          |
resource_type            | resource_status | updated_time
| stack_name            |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+
+-----+
| Controller             | 684e08e4-a304-4630-90fe-c9c24c3b45a7 |
OS::Heat::ResourceGroup | CREATE_FAILED | 2019-12-12T09:25:09Z
| overcloud
| 0                      | 2735e632-d8dd-4baa-9981-937cd1ac489f |
OS::Triple0::Controller | CREATE_FAILED | 2019-12-12T09:28:25Z
| overcloud-Controller-65ojpltgs3jd
| NetworkDeployment     | d6d8cab5-47a1-4020-bd63-431c3cc41d83 |
OS::Triple0::SoftwareDeployment | CREATE_FAILED | 2019-12-12T09:28:27Z
| overcloud-Controller-65ojpltgs3jd-0-fzjjcdw7sghj |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+
+-----+

# echo -e `heat deployment-show [physical_resource_id]
WARNING (shell) "heat deployment-show" is deprecated, please use "openstack
software deployment show" instead
{ "status": "FAILED", "server_id": "8e912488-5e86-4db2-8c2a-2fe00b21e7eb",
"config_id": "342e9b47-39ab-48af-8743-aab783e8b508", "output_values": {
"deploy_stdout": "Device has generated MAC, skipping.
Device has generated MAC, skipping.
ERROR: configuration of safe defaults failed.
", "deploy_stderr": "+ '[' -n '{"network_config": [{"addresses":
[{"ip_netmask": "10.10.10.21/24"}], "name": "nic1", "routes":
```

```
[{"ip_netmask": "169.254.169.254/32", "next_hop": "192.168.24.1"}],
{"type": "interface", "use_dhcp": false}, {"addresses":
[{"ip_netmask": "10.10.20.10/24"}], "name": "nic2", "type":
"interface", "use_dhcp": false}, {"addresses": [{"ip_netmask":
"10.10.40.6/24"}], "members": [{"name": "nic6", "type":
"interface"}], "name": "br-ex", "type": "ovs_bridge",
"use_dhcp": false}, {"addresses": [{"ip_netmask":
"10.10.30.12/24"}], "name": "nic3", "type": "interface",
"use_dhcp": false}, {"addresses": [{"ip_netmask":
"10.10.51.15/24"}], "name": "nic5", "type": "interface",
"use_dhcp": false}}] ']'
+ '[' -z '' ']'
+ trap configure_safe_defaults EXIT
+ mkdir -p /etc/os-net-config
+ echo '{"network_config": [{"addresses": [{"ip_netmask":
"10.10.10.21/24"}], "name": "nic1", "routes": [{"ip_netmask":
"169.254.169.254/32", "next_hop": "192.168.24.1"}], "type":
"interface", "use_dhcp": false}, {"addresses": [{"ip_netmask":
"10.10.20.10/24"}], "name": "nic2", "type": "interface",
"use_dhcp": false}, {"addresses": [{"ip_netmask": "10.10.40.6/24"}],
"members": [{"name": "nic6", "type": "interface"}], "name":
"br-ex", "type": "ovs_bridge", "use_dhcp": false}, {"addresses":
[{"ip_netmask": "10.10.30.12/24"}], "name": "nic3", "type":
"interface", "use_dhcp": false}, {"addresses": [{"ip_netmask":
"10.10.51.15/24"}], "name": "nic5", "type": "interface",
"use_dhcp": false}}]}'
++ type -t network_config_hook
...
```

From: <https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://atl.kr/dokuwiki/doku.php/openstack_overcloud_%EC%84%A4%EC%B9%98_%EC%8B%9C_%EC%97%90%EB%9F%AC%EB%A9%94%EC%84%B8%EC%A7%80_%ED%99%95%EC%9D%B8?rev=1587523290

Last update: 2020/04/22 02:41

