

reloadable **development mode** 3
reloadable 3
development mode 4

Last
update:
2015/09/23
03:03

reloadable_
_development_mode

https://atl.kr/dokuwiki/doku.php/reloadable_%EC%86%8D%EC%84%B1%EA%B3%BC_development_mode

reloadable

development mode

reloadable

: <https://tomcat.apache.org/tomcat-7.0-doc/config/context.html>

reloadable	Set to <code>true</code> if you want Catalina to monitor classes in <code>/WEB-INF/classes/</code> and <code>/WEB-INF/lib</code> for changes, and automatically reload the web application if a change is detected. This feature is very useful during application development, but it requires significant runtime overhead and is not recommended for use on deployed production applications. That's why the default setting for this attribute is <code>false</code> . You can use the Manager web application, however, to trigger reloads of deployed applications on demand.
------------	---

“true” (:false)

`/WEB-INF/classes/`
`/WEB-INF/lib/`

Context Reload가 WEB-INF/web.xml
 reloadable="false" reload가
 reload가 conf/context.xml

```
<Context sessionCookieName="${tomcat.engine.sessionCookieName}"
reloadable="false">

  <!-- Default set of monitored resources -->
  <WatchedResource>WEB-INF/web.xml</WatchedResource>

  <!-- Uncomment this to disable session persistence across Tomcat
restarts -->
  <!--
  <Manager pathname="" />
  -->

  <!-- Uncomment this to enable Comet connection tacking (provides events
on session expiration as well as webapp lifecycle) -->
  <!--
  <Valve
className="org.apache.catalina.valves.CometConnectionManagerValve" />
  -->

</Context>
```

`<WatchedResource>WEB-INF/web.xml</WatchedResource>`

web.xml context reload

development mode "false" jsp . (,)

development mode

: <http://tomcat.apache.org/tomcat-7.0-doc/jasper-howto.html>

- development mode = true
- true jsp reload가
- false jsp reload

```
<servlet>
  <servlet-name>jsp</servlet-name>
  <servlet-class>org.apache.jasper.servlet.JspServlet</servlet-class>
  <init-param>
    <param-name>fork</param-name>
    <param-value>>false</param-value>
  </init-param>
  <init-param>
    <param-name>development</param-name>
    <param-value>>true</param-value>
  </init-param>
  <init-param>
    <param-name>xpoweredBy</param-name>
    <param-value>>false</param-value>
  </init-param>
  <load-on-startup>3</load-on-startup>
</servlet>
```

From:
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:
https://atl.kr/dokuwiki/doku.php/reloadable_%EC%86%8D%EC%84%B1%EA%B3%BC_development_mode

Last update: 2015/09/23 03:03

