

reloadable **development mode** 3
reloadable 3
development mode 4

reloadable

development mode

reloadable

: <https://tomcat.apache.org/tomcat-7.0-doc/config/context.html>

reloadable	Set to <code>true</code> if you want Catalina to monitor classes in <code>/WEB-INF/classes/</code> and <code>/WEB-INF/lib</code> for changes, and automatically reload the web application if a change is detected. This feature is very useful during application development, but it requires significant runtime overhead and is not recommended for use on deployed production applications. That's why the default setting for this attribute is <code>false</code> . You can use the Manager web application, however, to trigger reloads of deployed applications on demand.
------------	---

`"true"` (`:false`)

```
/WEB-INF/classes/  
/WEB-INF/lib/
```

Context Reload가

```
/WEB-INF/web.xml
```

`reloadable="false"`

reload가

```
conf/context.xml
```

reload가 .

```
<Context sessionCookieName="${tomcat.engine.sessionCookieName}"  
reloadable="false">  
  
  <!-- Default set of monitored resources -->  
  <WatchedResource>WEB-INF/web.xml</WatchedResource>  
  
  <!-- Uncomment this to disable session persistence across Tomcat  
restarts -->  
  <!--  
  <Manager pathname="" />  
  -->  
  
  <!-- Uncomment this to enable Comet connection tacking (provides events  
on session expiration as well as webapp lifecycle) -->  
  <!--  
  <Valve  
className="org.apache.catalina.valves.CometConnectionManagerValve" />
```

-->

</Context>

```
<WatchedResource>WEB-INF/web.xml</WatchedResource> web.xml
    context reload
        "false" jsp . ( ,
development mode )
```

development mode

: <http://tomcat.apache.org/tomcat-7.0-doc/jasper-howto.html>

- development mode = true
- true jsp reload가
- false jsp reload

```
<servlet>
  <servlet-name>jsp</servlet-name>
  <servlet-class>org.apache.jasper.servlet.JspServlet</servlet-class>
  <init-param>
    <param-name>fork</param-name>
    <param-value>>false</param-value>
  </init-param>
  <init-param>
    <param-name>development</param-name>
    <param-value>>true</param-value>
  </init-param>
  <init-param>
    <param-name>xpoweredBy</param-name>
    <param-value>>false</param-value>
  </init-param>
  <load-on-startup>3</load-on-startup>
</servlet>
```

From: <https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://atl.kr/dokuwiki/doku.php/reloadable_%EC%86%8D%EC%84%B1%EA%B3%BC_development_mode?rev=1442977350

Last update: 2015/09/23 03:02

