목차

RHEL7 locale 변경 3
변경 가능한 로케일 확인 3
locale 추가 3

RHEL7 locale 변경

RHEL 7 에서 로케일 변경하는 방법입니다.

변경 가능한 로케일 확인

```
# locale -a
또는
# localectl list-locales
```

locale 추가

만약 위의 명령어로 확인했을때 변경을 원하는 로케일이 없는경우 해당 로케일 패키지를 먼저 설치해야 한다.

- `yum-langpacks.noarch` yum 플러그인을 우선 설치한다.

```
# yum install yum-langpacks
```

- 원하는 언어목록을 확인

```
# yum langlist
```

- 해당 언어 패키지 설치

```
# yum langinstall <lang>

# yum langinstall ko_KR
```

현재 사용가능한 한글관련 로케일

```
# localectl list-locales | grep -i ko
ko_KR
ko_KR.euckr
ko_KR.utf8
kok_IN
kok_IN.utf8
korean
korean.euc
ru_RU.koi8r
ru_UA.koi8u
```

```
tg_TJ.koi8t
uk_UA.koi8u
```

utf8 로 변경

```
 # localectl set-locale LANG=ko_KR.utf8
```

수동으로 변경시는 /etc/locale.conf 파일을 만들어 아래 내용 추가

```
LANG=ko_KR.utf8
```

서버 부팅 후 로케일 설정 확인

```
# locale
LANG=ko_KR.utf8
LC_CTYPE="ko_KR.utf8"
LC_NUMERIC="ko_KR.utf8"
LC_TIME="ko_KR.utf8"
LC_COLLATE="ko_KR.utf8"
LC_MONETARY="ko_KR.utf8"
LC_MESSAGES="ko_KR.utf8"
LC_PAPER="ko_KR.utf8"
LC_NAME="ko_KR.utf8"
LC_ADDRESS="ko_KR.utf8"
LC_TELEPHONE="ko_KR.utf8"
LC_MEASUREMENT="ko_KR.utf8"
LC_IDENTIFICATION="ko_KR.utf8"
LC_ALL=

# cat /etc/locale.conf
LANG=ko_KR.utf8
```

From:
https://atl.kr/dokuwiki/ - **AllThatLinux!**

Permanent link:
https://atl.kr/dokuwiki/doku.php/rhel7_locale_%EB%B3%80%EA%B2%BD

Last update: **2021/03/03 08:12**