

**VirtualBMC (vbmc)** ..... 3

가 ..... 3

..... 4



# VirtualBMC (vbmc)

```
yum -y install centos-release-openstack-train
yum -y install python2-virtualbmc

# vbmc /
vbmc add ik-metal0 --username admin --password secret@1337 --port 6230
vbmc start ik-metal0

# ipmi
ipmitool -I lanplus -U admin -P secret@1337 -H 10.80.80.1 -p 6230 power
status
```

## 가

: <https://ikhsanputra.com/posts/2020-03-16-install-virtualbmc-on-centos-7/>

```
yum -y update
yum -y install python3-pip python3-devel gcc libvirt-devel ipmitool
pip3 install --upgrade pip
pip3 install virtualbmc

#
vbmcd
vbmc list

# vbmc /
vbmc add ik-metal0 --username admin --password secret@1337 --port 6230
vbmc start ik-metal0

# ipmi
ipmitool -I lanplus -U admin -P secret@1337 -H 10.80.80.1 -p 6230 power
status
```

```
        vbmcd                가                가
pid                .
```

```
rm -rf ~/master.pid
rm -rf ~/.vbmc
```

- [VBMC](#)     [TripleO](#)     [IPMI](#)
- <https://docs.openstack.org/virtualbmc/latest/user/index.html>
- <https://docs.openstack.org/project-deploy-guide/tripleo-docs/latest/environments/virtualbmc.html>
- [https://access.redhat.com/documentation/ko-kr/red\\_hat\\_openshift\\_platform/11/html/director\\_installation\\_and\\_usage/appe-power\\_management\\_drivers](https://access.redhat.com/documentation/ko-kr/red_hat_openshift_platform/11/html/director_installation_and_usage/appe-power_management_drivers)

From:  
<https://at1.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:  
[https://at1.kr/dokuwiki/doku.php/virtualbmc\\_vbmc\\_%EC%84%A4%EC%A0%95%ED%95%98%EA%B8%B0?rev=1612503384](https://at1.kr/dokuwiki/doku.php/virtualbmc_vbmc_%EC%84%A4%EC%A0%95%ED%95%98%EA%B8%B0?rev=1612503384)

Last update: **2021/02/05 05:36**

