

**Bluetooth Speaker Auto connect |** ..... 3  
..... 3  
..... 4  
..... 4



# Bluetooth Speaker Auto connect |

— 2021/05/01 12:29



CentOS / RHEL

```

MAC Address
bluetoothctl devices
가

```

```

[koov@home ~]$ bluetoothctl devices
Device 04:FE:A1:04:0F:5B Britz BR-1700BT

```

```

MAC Address 04:FE:A1:04:0F:5B

```

```

bluetoothctl info <MAC>

```

```

[koov@home ~]$ bluetoothctl info 04:FE:A1:04:0F:5B
Device 04:FE:A1:04:0F:5B (public)
  Name: Britz BR-1700BT
  Alias: Britz BR-1700BT
  Class: 0x00240428
  Icon: audio-card
  Paired: yes
  Trusted: yes
  Blocked: no
  Connected: yes
  LegacyPairing: no
  UUID: Audio Sink (0000110b-0000-1000-8000-00805f9b34fb)
  UUID: A/V Remote Control Target (0000110c-0000-1000-8000-00805f9b34fb)
  UUID: A/V Remote Control (0000110e-0000-1000-8000-00805f9b34fb)

```

가

Paired: yes Trusted: yes

```
[koov@home ~]$ bluetoothctl pair 04:FE:A1:04:0F:5B
Attempting to pair with 04:FE:A1:04:0F:5B

[koov@home ~]$ bluetoothctl trust 04:FE:A1:04:0F:5B
Changing 04:FE:A1:04:0F:5B trust succeeded
```

가 가 가 가

/etc/pulse/default.pa

```
.ifexists module-bluetooth-discover.so
load-module module-bluetooth-discover
load-module module-switch-on-connect # <- 가
.endif
```

: <https://askubuntu.com/questions/922072/autoconnect-to-a-bluetooth-speaker-in-ubuntu-16-04>

X-Windows 가

가

( koov ) bin

```
[koov@home ~]$ mkdir ~/bin
[koov@home ~]$ vim ~/bin/btautoconnect.sh
```

btautoconnect.sh

```
#!/bin/bash
```

```
bluetoothctl connect 04:FE:A1:04:0F:5B
```

```
(04:FE:A1:04:0F:5B)
```

```
[koov@home ~]$ chmod +x ~/bin/btautoconnect.sh
```

```
X-Windows
```

```
가
```

```
btautoconnect.desktop
```

```
[koov@home ~]$ mkdir -p ~/.config/autostart
```

```
[koov@home ~]$ vim ~/.config/autostart/btautoconnect.desktop
```

```
btautoconnect.desktop
```

```
[Desktop Entry]
Type=Application
Exec=/bin/bash /home/koov/bin/btautoconnect.sh
Hidden=false
NoDisplay=false
X-GNOME-Autostart-enabled=true
Name=BTAutoConnect
X-GNOME-Autostart-Delay=5
Comment=Starts Bluetooth speaker
```

```
(koov) X-Windows
```

```
가
```

[:https://askubuntu.com/questions/1170809/how-do-i-get-a-bluetooth-speaker-to-auto-connect-at-login](https://askubuntu.com/questions/1170809/how-do-i-get-a-bluetooth-speaker-to-auto-connect-at-login)

From: <https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link: [https://atl.kr/dokuwiki/doku.php/bluetooth\\_speaker\\_auto\\_connect](https://atl.kr/dokuwiki/doku.php/bluetooth_speaker_auto_connect)

Last update: **2021/05/01 03:30**



