

<b>Bluetooth Speaker Auto connect  </b>	.....	3
	.....	3
	.....	4
	.....	4



# Bluetooth Speaker Auto connect |

— 2021/05/01 12:29



CentOS / RHEL

MAC Address 가  
bluetoothctl devices

```
[koov@home ~]$ bluetoothctl devices  
Device 04:FE:A1:04:0F:5B Britz BR-1700BT
```

MAC Address 04:FE:A1:04:0F:5B

bluetoothctl info <MAC>

```
[koov@home ~]$ bluetoothctl info 04:FE:A1:04:0F:5B  
Device 04:FE:A1:04:0F:5B (public)  
  Name: Britz BR-1700BT  
  Alias: Britz BR-1700BT  
  Class: 0x00240428  
  Icon: audio-card  
  Paired: yes  
  Trusted: yes  
  Blocked: no  
  Connected: yes  
  LegacyPairing: no  
  UUID: Audio Sink          (0000110b-0000-1000-8000-00805f9b34fb)  
  UUID: A/V Remote Control Target (0000110c-0000-1000-8000-00805f9b34fb)  
  UUID: A/V Remote Control      (0000110e-0000-1000-8000-00805f9b34fb)
```

가

Paired: yes Trusted: yes

```
[koov@home ~]$ bluetoothctl pair 04:FE:A1:04:0F:5B
Attempting to pair with 04:FE:A1:04:0F:5B
```

```
[koov@home ~]$ bluetoothctl trust 04:FE:A1:04:0F:5B
Changing 04:FE:A1:04:0F:5B trust succeeded
```

가

가

가

가

/etc/pulse/default.pa

```
.ifeffects module-bluetooth-discover.so
load-module module-bluetooth-discover
load-module module-switch-on-connect      # <-
.endif
```

: <https://askubuntu.com/questions/922072/autoconnect-to-a-bluetooth-speaker-in-ubuntu-16-04>

X-Windows

가

가

( koov ) bin

```
[koov@home ~]$ mkdir ~/bin
[koov@home ~]$ vim ~/bin/btautoconnect.sh
```

btautoconnect.sh

```
#!/bin/bash
```

```
bluetoothctl connect 04:FE:A1:04:0F:5B
```

(04:FE:A1:04:0F:5B)

```
[koov@home ~]$ chmod +x ~/bin/btautoconnect.sh
```

X-Windows

가

btautoconnect.desktop

```
[koov@home ~]$ mkdir -p ~/.config/autostart
```

```
[koov@home ~]$ vim ~/.config/autostart/btautoconnect.desktop
```

btautoconnect.desktop

```
[Desktop Entry]
Type=Application
Exec=/bin/bash /home/koov/bin/btautoconnect.sh
Hidden=false
NoDisplay=false
X-GNOME-Autostart-enabled=true
Name=BTAutoConnect
X-GNOME-Autostart-Delay=5
Comment=Starts Bluetooth speaker
```

(koov) X-Windows

가

:<https://askubuntu.com/questions/1170809/how-do-i-get-a-bluetooth-speaker-to-auto-connect-at-login>

From:  
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:  
<https://atl.kr/dokuwiki/doku.php/bluetooth Speaker Auto Connect>

Last update: 2021/05/01 03:30



