

JBoss EAP 7 Tuning CLI script 3

JBoss EAP 7 Tuning CLI script

default / runtime value query

```
/subsystem=undertow/server=default-server/http-listener=default:read-resource(include-defaults=true,include-runtime=true)
```

```
##### default thread pool
```

```
/subsystem=io/worker=default/:write-attribute(name=task-core-threads,value=256)
```

```
/subsystem=io/worker=default/:write-attribute(name=task-max-threads,value=512)
```

```
/subsystem=io/worker=default/:write-attribute(name=io-threads,value=128)
```

```
##### Session Timeout
```

```
/subsystem=undertow/servlet-container=default:write-attribute(name=default-session-timeout,value=60)
```

```
##### header
```

```
/subsystem=undertow/configuration=filter/response-header=server-header:remove
```

```
/subsystem=undertow/configuration=filter/response-header=x-powered-by-header:remove
```

```
/subsystem=undertow/configuration=filter/response-header=server-header:add(header-name="Server",header-value="JBoss-EAP/7")
```

```
/subsystem=undertow/configuration=filter/response-header=x-powered-by-header:add(header-name="X-Powered-By",header-value="Undertow/1")
```

```
##### welcome-content
```

```
/subsystem=undertow/server=default-server/host=default-host/location=\\/:remove
```

```
/subsystem=undertow/configuration=handler/file=welcome-content:remove
```

```
##### http listener , AJP HTTPS
```

```
##### max-post-size 10485760 = 10MB
```

```
/subsystem=undertow/server=default-server/http-listener=default:write-attribute(name=max-post-size,value=10485760L)
```

```
/subsystem=undertow/server=default-server/ajp-listener=ajp:write-attribute(name=max-post-size,value=10485760L)
```

```
##### max-header-size 1048576 = 1MB
```

```
/subsystem=undertow/server=default-server/http-listener=default:write-attribute(name=max-header-size,value=1048576)
```

```
##### max-headers
```

```
/subsystem=undertow/server=default-server/http-listener=default:write-attribute(name=max-headers,value=200)
```

```
##### max-parameters  
/subsystem=undertow/server=default-server/http-listener=default:write-  
attribute(name=max-parameters,value=1000)
```

From:

<https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:

https://atl.kr/dokuwiki/doku.php/jboss_eap_7_tuning_cli_script?rev=1643109116

Last update: **2022/01/25 11:11**

