

<b>Openshift 4</b>	.....	3
	.....	3
	.....	3
IPI	.....	3
UPI	.....	3



# Openshift 4

## Openshift 4

- IPI: Installer Provisioned Infrastructure  
가 bootstrap . provisioner  
master, worker
- UPI: User Provisioned Infrastructure  
bastion bootstrap, master, worker

### IPI

	vCPU			NIC # 1	NIC # 2
Master Node # 1	4	16 GB	128 GB	Provisioning	Baremetal
Master Node # 2	4	16 GB	128 GB	Provisioning	Baremetal
Master Node # 3	4	16 GB	128 GB	Provisioning	Baremetal
Worker Node # 1	4	8 GB	128 GB	Provisioning	Baremetal
Worker Node # 2	4	8 GB	128 GB	Provisioning	Baremetal
Provisioner	4	16 GB	128 GB	Provisioning	Baremetal

### UPI

	vCPU			NIC # 1	NIC # 2
Master Node # 1	4	16 GB	128 GB	Provisioning	Baremetal
Master Node # 2	4	16 GB	128 GB	Provisioning	Baremetal
Master Node # 3	4	16 GB	128 GB	Provisioning	Baremetal
Worker Node # 1	4	8 GB	128 GB	Provisioning	Baremetal
Worker Node # 2	4	8 GB	128 GB	Provisioning	Baremetal
Bootstrap	4	16 GB	128 GB	Provisioning	Baremetal
Bastion	2	4 GB	128 GB	Provisioning	Baremetal

From:  
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:  
[https://atl.kr/dokuwiki/doku.php/openshift\\_4\\_%ED%81%B4%EB%9F%AC%EC%8A%A4%ED%84%B0\\_%EA%B5%AC%EC%B6%95?rev=1620113523](https://atl.kr/dokuwiki/doku.php/openshift_4_%ED%81%B4%EB%9F%AC%EC%8A%A4%ED%84%B0_%EA%B5%AC%EC%B6%95?rev=1620113523)

Last update: 2021/05/04 07:32

