

<b>reloadable</b>	<b>development mode</b>	.....	3
<i>reloadable</i>		.....	3
<i>development mode</i>		.....	3

Last  
update:  
2015/09/09  
04:50

reloadable  
\_development\_mode

[https://atl.kr/dokuwiki/doku.php/reloadable\\_%EC%86%8D%EC%84%B1%EA%B3%BC\\_development\\_mode?rev=1441774232](https://atl.kr/dokuwiki/doku.php/reloadable_%EC%86%8D%EC%84%B1%EA%B3%BC_development_mode?rev=1441774232)

---

# reloadable

# development mode

## reloadable

: <https://tomcat.apache.org/tomcat-7.0-doc/config/context.html>

reloadable	Set to <code>true</code> if you want Catalina to monitor classes in <code>/WEB-INF/classes/</code> and <code>/WEB-INF/lib</code> for changes, and automatically reload the web application if a change is detected. This feature is very useful during application development, but it requires significant runtime overhead and is not recommended for use on deployed production applications. That's why the default setting for this attribute is <code>false</code> . You can use the <a href="#">Manager</a> web application, however, to trigger reloads of deployed applications on demand.
------------	---

“true” ( :false)

`/WEB-INF/classes/`  
`/WEB-INF/lib/`

Context Reload가

`/WEB-INF/web.xml`  
`/META-INF/context.xml`

reloadable="false" reload가  
“false” jsp .( ,  
development mode )

## development mode

: <http://tomcat.apache.org/tomcat-7.0-doc/jasper-howto.html>

- development mode = true
- true jsp reload가
- false jsp reload

```
<servlet>
    <servlet-name>jsp</servlet-name>
    <servlet-class>org.apache.jasper.servlet.JspServlet</servlet-class>
    <init-param>
        <param-name>fork</param-name>
        <param-value>false</param-value>
    </init-param>
    <init-param>
```

Last  
update:  
2015/09/09  
04:50

reloadable\_  
\_development\_mode https://atl.kr/dokuwiki/doku.php/reloadable\_%EC%86%8D%EC%84%B1%EA%B3%BC\_development\_mode?rev=1441774232

```
<param-name>development</param-name>
<param-value>true</param-value>
</init-param>
<init-param>
<param-name>xpoweredBy</param-name>
<param-value>false</param-value>
</init-param>
<load-on-startup>3</load-on-startup>
</servlet>
```

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

[https://atl.kr/dokuwiki/doku.php/reloadable\\_%EC%86%8D%EC%84%B1%EA%B3%BC\\_development\\_mode?rev=1441774232](https://atl.kr/dokuwiki/doku.php/reloadable_%EC%86%8D%EC%84%B1%EA%B3%BC_development_mode?rev=1441774232)

Last update: 2015/09/09 04:50

