

- Ironic Baremetal Service** 3
- 4
- 6
- 6
- Inspection 가 7
- Provision 8
- Clean 8
- Ironic(Stein)*** ***(devstack)*** 9
- Ironic*** 16
- Provisioning 16
- Cleaning 17
- Deploy User 17
- Ironic Node 19
- Ironic Conductor*** 22
- Ironic*** 24
- Ironic Python Agent(IPA)*** 25
- Ironic Console*** 26
- Ironic*** 26
- 27

Ironic Baremetal Service

Ironic 가 OpenStack Cloud Compute(nova), Network(neutron), Image(glance), OpenStack Identity(keystone), Object(swift)

PXE IPMI

, Compute 가 : <https://docs.openstack.org/ironic/latest/>

가 , 가 Ironic

OpenStack OpenStack

- Ironic Standalone(Bifrost): Ironic
- OpenStack (Nova): Ironic Nova

: Bifrost Standalone Ironic Ansible

Ironic OpenStack 가 가 가 가 PXE IPMI Ironic Ironic 가 Ironic API, (: Kubernetes


Ironic :

1. :
2. **OpenStack** :


Ironic OpenStack :

1. **Keystone:**
2. **Glance:**
3. **Nova:** Ironic
4. **Ironic:**
5. **Neutron:**
6. **Cinder:**
7. **Ceilometer:** IPMI OpenStack
8. **Swift:**

Figure 1.1. Conceptual Architecture




<https://is-cloud.blog.csdn.net>



<https://is-cloud.blog.csdn.net>

- 1. **node:** , CPU, Ironic
- 2. **chassis:** ,
- 3. **port:** , MAC , LLDP
- 4. **portgroup:**
- 5. **conductor:** ironic-conductor
- 6. **volume connector/target:**



<https://is-cloud.blog.csdn.net>

Inspection 가


Ironic Inspector

Ironic

Ironic Inspector가


가 IPA(Ironic Python Agent) Ironic Inspector가 . IPA
 , Ironic Inspector . IPA가 CPU ,
 CPU Feature Flag, Scheduler , SDN 가 IP, MAC , Nova
 LLDP() . LLDP SDN
 , Chassis ID Port ID SDN

Inspection : [] [] [] [가] .



<https://is-cloud.blog.csdn.net>

- enroll: , 가
- verifying: 가 manage API , Ironic 가
- manageable: 가 ,
- inspecting: Ironic , CPU, RAM, , NIC
- available: 가 manageable provide API , cleaning 가 (CPU, RAM, , NIC)가



- Inspection Provide Cleaning 가 가
- Provision Delete Cleaning 가 가

Ironic(Stein) (devstack)

<https://docs.openstack.org/ironic/stein/contributor/dev-quickstart.html#deploying-ironic-with-devstack>

devstack

```
git clone https://git.openstack.org/openstack-dev/devstack.git -b
stable/stein
sudo ./devstack/tools/create-stack-user.sh
sudo su - stack
```

local.conf

```
[[local|localrc]]
HOST_IP=192.168.1.100

# Use TryStack(99cloud) git mirror
GIT_BASE=http://git.trystack.cn
#GIT_BASE=https://git.openstack.org

# Reclone each time
RECLONE=no

# Enable Logging
DEST=/opt/stack
LOGFILE=$DEST/logs/stack.sh.log
VERBOSE=True
LOG_COLOR=True
SCREEN_LOGDIR=$DEST/logs
LOGDAYS=1
```

```
# Define images to be automatically downloaded during the DevStack built
process.
DOWNLOAD_DEFAULT_IMAGES=False
IMAGE_URLS="http://download.cirros-cloud.net/0.3.4/cirros-0.3.4-x86_64-disk.
img"

# use TryStack git mirror
GIT_BASE=http://git.trystack.cn
NOVNC_REPO=http://git.trystack.cn/kanaka/noVNC.git
SPICE_REPO=http://git.trystack.cn/git/spice/sice-html5.git

# Apache Frontend
ENABLE_HTTPD_MOD_WSGI_SERVICES=False

# IP Version
IP_VERSION=4

# Credentials
ADMIN_PASSWORD=password
DATABASE_PASSWORD=password
RABBIT_PASSWORD=password
SERVICE_PASSWORD=password
SERVICE_TOKEN=password
SWIFT_HASH=password
SWIFT_TEMPURL_KEY=password

# Enable Ironic plugin
enable_plugin ironic https://git.openstack.org/openstack/ironic stable/stein

# Disable nova novnc service, ironic does not support it anyway.
disable_service n-novnc

# Enable Swift for the direct deploy interface.
enable_service s-proxy
enable_service s-object
enable_service s-container
enable_service s-account

# Cinder
VOLUME_GROUP_NAME="stack-volumes"
VOLUME_NAME_PREFIX="volume-"
VOLUME_BACKING_FILE_SIZE=100G

# Neutron
ENABLED_SERVICES+=,q-svc,q-agt,q-dhcp,q-l3,q-meta
# By default, DevStack creates a 10.0.0.0/24 network for instances.
# If this overlaps with the hosts network, you may adjust with the
# following.
NETWORK_GATEWAY=10.1.0.1
FIXED_RANGE=10.1.0.0/24
FIXED_NETWORK_SIZE=256
```

```
# Swift temp URL's are required for the direct deploy interface
SWIFT_ENABLE_TEMPURLS=True

# Create 3 virtual machines to pose as Ironic's baremetal nodes.
IRONIC_VM_COUNT=3
IRONIC_BAREMETAL_BASIC_OPS=True
DEFAULT_INSTANCE_TYPE=baremetal

# Enable additional hardware types, if needed.
#IRONIC_ENABLED_HARDWARE_TYPES=ipmi,fake-hardware
# Don't forget that many hardware types require enabling of additional
# interfaces, most often power and management:
#IRONIC_ENABLED_MANAGEMENT_INTERFACES=ipmitool,fake
#IRONIC_ENABLED_POWER_INTERFACES=ipmitool,fake
# The 'ipmi' hardware type's default deploy interface is 'iscsi'.
# This would change the default to 'direct':
#IRONIC_DEFAULT_DEPLOY_INTERFACE=direct

# Change this to alter the default driver for nodes created by devstack.
# This driver should be in the enabled list above.
IRONIC_DEPLOY_DRIVER=ipmi

# The parameters below represent the minimum possible values to create
# functional nodes.
IRONIC_VM_SPECS_RAM=1280
IRONIC_VM_SPECS_DISK=10

# Size of the ephemeral partition in GB. Use 0 for no ephemeral partition.
IRONIC_VM_EPHEMERAL_DISK=0

# To build your own IPA ramdisk from source, set this to True
IRONIC_BUILD_DEPLOY_RAMDISK=False

VIRT_DRIVER=ironic

# Log all output to files
LOGFILE=/opt/stack/devstack.log
LOGDIR=/opt/stack/logs
IRONIC_VM_LOG_DIR=/opt/stack/ironic-bm-logs
```

```
[root@localhost ~]# openstack compute service list
+-----+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+-----+
| ID | Binary                | Host                | Zone   | Status | State |
| Updated At                |                    |        |        |        |      |
+-----+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+-----+
| 3 | nova-scheduler        | localhost.localdomain | internal | enabled | up   |
```

```

| 2019-05-03T18:56:18.000000 |
| 6 | nova-consoleauth | localhost.localdomain | internal | enabled | up
| 2019-05-03T18:56:22.000000 |
| 7 | nova-conductor   | localhost.localdomain | internal | enabled | up
| 2019-05-03T18:56:14.000000 |
| 1 | nova-conductor   | localhost.localdomain | internal | enabled | up
| 2019-05-03T18:56:15.000000 |
| 3 | nova-compute     | localhost.localdomain | nova     | enabled | up
| 2019-05-03T18:56:18.000000 |
+-----+-----+-----+-----+-----+-----+-----+
-+-----+

```

[root@localhost ~]# openstack network agent list

```

+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| ID | Agent Type | Host |
| Availability Zone | Alive | State | Binary |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| 52f23bda-a645-4459-bcac-686d98d23345 | Open vSwitch agent |
localhost.localdomain | None | :- ) | UP | neutron-
openvswitch-agent |
| 7113312f-b0b7-4ce8-ab15-428768b30855 | L3 agent |
localhost.localdomain | nova | :- ) | UP | neutron-l3-agent
|
| a45fb074-3b24-4b9e-8c8a-43117f6195f2 | Metadata agent |
localhost.localdomain | None | :- ) | UP | neutron-
metadata-agent |
| f207648b-03f3-4161-872e-5210f29099c6 | DHCP agent |
localhost.localdomain | nova | :- ) | UP | neutron-dhcp-
agent |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+

```

[root@localhost ~]# openstack volume service list

```

+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| Binary | Host | Zone | Status |
| State | Updated At |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| cinder-scheduler | localhost.localdomain | nova | enabled | up
| 2019-05-03T18:56:54.000000 |
| cinder-volume | localhost.localdomain@lvmdriver-1 | nova | enabled | up
| 2019-05-03T18:56:53.000000 |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+

```

[root@localhost ~]# openstack baremetal driver list

```

+-----+-----+-----+-----+-----+-----+-----+
| Supported driver(s) | Active host(s) |

```

```
+-----+-----+
| fake-hardware      | localhost      |
| ipmi               | localhost      |
+-----+-----+
```

```
[root@localhost ~]# openstack baremetal node list
```

```
+-----+-----+-----+-----+-----+
--+-+-----+-----+
| UUID                               | Name   | Instance UUID | Power
State | Provisioning State | Maintenance |
+-----+-----+-----+-----+
--+-+-----+-----+
| adda54fb-1038-4634-8d82-53922e875a1f | node-0 | None          | power off
| available                          | False  |               |
| 6952e923-11ae-4506-b010-fd7a3c4278f5 | node-1 | None          | power off
| available                          | False  |               |
| f3b8fe69-a840-42dd-9cbf-217be8a95431 | node-2 | None          | power off
| available                          | False  |               |
+-----+-----+-----+-----+
--+-+-----+-----+
```

```
[root@localhost ~]# openstack server create --flavor baremetal --image
cirros-0.4.0-x86_64-disk --key-name default --nic net-id=5c86f931-64da-4c69-
a0f1-e2da6d9dd082 VM1
```

```
+-----+-----+
| Field                               | Value
+-----+-----+
--+-+-----+-----+
| OS-DCF:diskConfig                  | MANUAL
| OS-EXT-AZ:availability_zone         |
| OS-EXT-SRV-ATTR:host                | None
| OS-EXT-SRV-ATTR:hypervisor_hostname | None
| OS-EXT-SRV-ATTR:instance_name      |
| OS-EXT-STS:power_state              | NOSTATE
| OS-EXT-STS:task_state               | scheduling
| OS-EXT-STS:vm_state                | building
| OS-SRV-USG:launched_at              | None
+-----+-----+
```

```
| OS-SRV-USG:terminated_at | None
| accessIPv4 |
| accessIPv6 |
| addresses |
| adminPass | k3TgBf5Xjsqv
| config_drive |
| created | 2019-05-03T20:26:28Z
| flavor | baremetal (8f6fd22b-9bec-4b4d-
b427-7c333e47d2c2) |
| hostId |
| id | 70e9f2b1-a292-4e95-90d4-55864bb0a71d
| image | cirros-0.4.0-x86_64-disk (4ff12aca-
b762-436c-b98c-579ad2a21649) |
| key_name | default
| name | VM1
| progress | 0
| project_id | cbf936fc5e9d4cfcaa1dbc06cd9d2e3e
| properties |
| security_groups | name='default'
| status | BUILD
| updated | 2019-05-03T20:26:28Z
| user_id | 405fad83a4b3470faf7d6c616fe9f7f4
| volumes_attached |
```

```
+-----+
-----+
```

```
[root@localhost ~]# openstack baremetal node list
```

```
+-----+-----+-----+-----+
-----+-----+-----+-----+
| UUID | Name | Instance UUID |
| Power State | Provisioning State | Maintenance |
+-----+-----+-----+-----+
```

```

-----+-----+-----+-----+
| adda54fb-1038-4634-8d82-53922e875a1f | node-0 | None
| power off | available | False |
| 6952e923-11ae-4506-b010-fd7a3c4278f5 | node-1 | None
| power off | available | False |
| f3b8fe69-a840-42dd-9cbf-217be8a95431 | node-2 | 70e9f2b1-
a292-4e95-90d4-55864bb0a71d | power off | deploying | False
|
+-----+-----+-----+-----+
-----+-----+-----+-----+

```

[root@localhost ~]# openstack server list --long

```

+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| ID | Name | Status | Task State | Power
State | Networks | Image Name | Image ID |
| Flavor Name | Flavor ID | Availability Zone |
Host | Properties |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| 70e9f2b1-a292-4e95-90d4-55864bb0a71d | VM1 | ACTIVE | None |
Running | private=10.0.0.40 | cirros-0.4.0-x86_64-disk | 4ff12aca-
b762-436c-b98c-579ad2a21649 | baremetal | 8f6fd22b-9bec-4b4d-
b427-7c333e47d2c2 | nova | localhost.localdomain |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+

```

[root@localhost ~]# openstack baremetal node list

```

+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| UUID | Name | Instance UUID
| Power State | Provisioning State | Maintenance |
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+
| adda54fb-1038-4634-8d82-53922e875a1f | node-0 | None
| power off | available | False |
| 6952e923-11ae-4506-b010-fd7a3c4278f5 | node-1 | None
| power off | available | False |
| f3b8fe69-a840-42dd-9cbf-217be8a95431 | node-2 | 70e9f2b1-
a292-4e95-90d4-55864bb0a71d | power on | deploying | False
|
+-----+-----+-----+-----+-----+-----+-----+
-----+-----+-----+-----+-----+-----+-----+

```

[root@localhost ~]# ssh cirros@10.0.0.40

```
$
```

```
Ironi   OpenStack Nova
```

```
# nova.conf

[DEFAULT]
...
compute_driver = ironic.IronicDriver
```

Ironi

Provisioning

```
Provisioning
```

```
DHCP PXE
```

```
# /etc/neutron/plugins/ml2/ml2_conf.ini

[ml2_type_flat]
flat_networks = public, physnet1

[ovs]
datapath_type = system
bridge_mappings = public:br-ex, physnet1:br-eth2
tunnel_bridge = br-tun
local_ip = 172.22.132.93
```

OvS Provider

```
$ sudo ovs-vsctl add-br br-eth2
$ sudo ovs-vsctl add-port br-eth2 eth2
```

OvS

```
$ sudo systemctl restart devstack@q-svc.service
$ sudo systemctl restart devstack@q-agt.service
```



```
$ neutron net-create sharednet1 \
    --shared \
    --provider:network_type flat \
    --provider:physical_network physnet1

$ neutron subnet-create sharednet1 172.22.132.0/24 \
    --name sharedsubnet1 \
    --ip-version=4 --gateway=172.22.132.254 \
    --allocation-pool
start=172.22.132.180,end=172.22.132.200 \
    --enable-dhcp
```

: DHCP PXE IP .

Cleaning

ironic node clean Provisioning Cleaning 가 . Cleaning

```
# /etc/ironic/ironic.conf

[neutron]
cleaning_network = sharednet1
```

Ironic

```
$ sudo systemctl restart devstack@ir-api.service
$ sudo systemctl restart devstack@ir-cond.service
```

Deploy User

Deploy User Disk Image Builder . DevStack
Deploy

disk-image-builder

```
$ virtualenv dib
$ source dib/bin/activate
(dib) $ pip install diskimage-builder
```

User Image

```
$ cat <<EOF > k8s.repo
[kubernetes]
name=Kubernetes
baseurl=http://yum.kubernetes.io/repos/kubernetes-el7-x86_64
enabled=1
gpgcheck=0
repo_gpgcheck=0
gpgkey=https://packages.cloud.google.com/yum/doc/yum-key.gpg
      https://packages.cloud.google.com/yum/doc/rpm-package-key.gpg
EOF

$ DIB_YUM_REPO_CONF=k8s.repo \
  DIB_DEV_USER_USERNAME=kyle \
  DIB_DEV_USER_PWDLESS_SUDO=yes \
  DIB_DEV_USER_PASSWORD=r00tme \
  disk-image-create \
    centos7 \
    dhcp-all-interfaces \
    devuser \
    yum \
    epel \
    baremetal \
    -o k8s.qcow2 \
    -p vim,docker,kubelet,kubeadm,kubectl,kubernetes-cni

...
Converting image using qemu-img convert
Image file k8s.qcow2 created...

$ ls
dib k8s.d k8s.initrd k8s.qcow2 k8s.repo k8s.vmlinuz
```

Glance

```
# Kernel
$ openstack image create k8s.kernel \
  --public \
  --disk-format aki \
  --container-format aki < k8s.vmlinuz

# Initrd
$ openstack image create k8s.initrd \
  --public \
  --disk-format ari \
  --container-format ari < k8s.initrd

# Qcow2
$ export MY_VMLINUZ_UUID=$(openstack image list | awk '/k8s.kernel/ { print $2 }')
$ export MY_INITRD_UUID=$(openstack image list | awk '/k8s.initrd/ { print
```

```
$2 }')
$ openstack image create k8s \
    --public \
    --disk-format qcow2 \
    --container-format bare \
    --property kernel_id=$MY_VMLINUZ_UUID \
    --property ramdisk_id=$MY_INITRD_UUID < k8s.qcow2
```

Ironic Node

Ironic Node가
 (Ironic)가

```
$ ironic driver-list
+-----+-----+
| Supported driver(s) | Active host(s) |
+-----+-----+
| agent_ipmitool     | ironic-dev     |
| fake               | ironic-dev     |
| ipmi               | ironic-dev     |
| pxe_ipmitool       | ironic-dev     |
+-----+-----+
```

: , [Set up the drivers for the Bare Metal service](#) 가

Ironic

```
$ export DEPLOY_VMLINUZ_UUID=$(openstack image list | awk '/ipmitool.kernel/{ print $2 }')
$ export DEPLOY_INITRD_UUID=$(openstack image list | awk '/ipmitool.initramfs/{ print $2 }')
$ ironic node-create -d agent_ipmitool \
    -n bare-node-1 \
    -i ipmi_address=172.20.3.194 \
    -i ipmi_username=maas \
    -i ipmi_password=passwd \
    -i ipmi_port=623 \
    -i ipmi_terminal_port=9000 \
    -i deploy_kernel=$DEPLOY_VMLINUZ_UUID \
    -i deploy_ramdisk=$DEPLOY_INITRD_UUID
```

```
$ export NODE_UUID=$(ironic node-list | awk '/bare-node-1/ { print $2 }')
$ ironic node-update $NODE_UUID add \
    properties/cpus=4 \
    properties/memory_mb=8192 \
    properties/local_gb=100 \
    properties/root_gb=100 \
    properties/cpu_arch=x86_64
```


: 가 Ironic Inspector .
:

```
# /etc/ironic-inspector/dnsmasq.conf

no-daemon
port=0
interface=eth1
bind-interfaces
dhcp-range=172.22.132.200,172.22.132.210
dhcp-match=ipxe,175
dhcp-boot=tag:!ipxe,undionly.kpxe
dhcp-boot=tag:ipxe,http://172.22.132.93:3928/ironic-inspector.ipxe
dhcp-sequential-ip

$ devstack@ironic-inspector-dhcp.service
$ devstack@ironic-inspector.service
```

Inspection



Ironic

```
$ ironic port-create -n $NODE_UUID -a NODE_PXE_NIC_MAC_ADDRESS
```

Ironic

```
$ ironic node-validate $NODE_UUID
+-----+-----+-----+
| Interface | Result | Reason
|
+-----+-----+-----+
| boot      | False  | Cannot validate image information for node
8e6fd86a-8eed-4e24-a510-3f5ebb0a336a because one or more parameters are
missing from its instance_info. Missing are: ['ramdisk', 'kernel',
'image_source'] |
| console   | False  | Missing 'ipmi_terminal_port' parameter in node\'s
driver_info.
|
```

```

| deploy      | False | Cannot validate image information for node
8e6fd86a-8eed-4e24-a510-3f5ebb0a336a because one or more parameters are
missing from its instance_info. Missing are: ['ramdisk', 'kernel',
'image_source'] |
| inspect     | True  |
|
| management  | True  |
|
| network     | True  |
|
| power       | True  |
|
| raid        | True  |
|
| storage     | True  |
|
+-----+-----+-----+
-----
-----
-----+

```

: Ironic boot deploy가 False .

Ironic 가

```

$ ironic --ironic-api-version 1.34 node-set-provision-state $NODE_UUID
manage
$ ironic --ironic-api-version 1.34 node-set-provision-state $NODE_UUID
provide
$ ironic node-list
+-----+-----+-----+-----+
--+-----+-----+
| UUID                               | Name   | Instance UUID | Power
State | Provisioning State | Maintenance |
+-----+-----+-----+-----+
--+-----+-----+
| 0c20cf7d-0a36-46f4-ac38-721ff8bfb646 | bare-0 | None          | power off
| cleaning                            | False  |
+-----+-----+-----+-----+
--+-----+-----+

```

: Ironic 가 cleaning available .

Ironic Conductor


Conductor ,

. Conductor


가

Ironic

가 Conductor , Ironic 가
 Conductor .
 Conductor Ironic
 Conductor . Conductor 가 가 ,
 가 Conductor , 가 (: take-over clean-up)




<https://is-cloud.blog.csdn.net>



Ironic

Ironic

가 , , , 가



<https://is-cloud.blog.csdn.net>

1. **power:**
2. **boot:** ()
3. **deploy:**
4. **management:**
5. **raid:** RAID
6. **inspect:** 가
7. **console:**
8. **network:**
9. **storage:**

10. vendor:

Ironic

RESTful API

driver集合名称	driver名称	driver类别
agent_ipmitool	ipmi	power
	pxe	boot
	agent	deploy

Ironic Python Agent(IPA)

Ironic Python Agent, ramdisk . IPA

IPA

IPA

Ironic Conductor

initramfs

- **ironic-agent.kernel:**
- **ironic-agent.initramfs:** IPA Ironic Conductor

IPA :

-
-
-
-
- RAID

IPA :

```
disk-image-create -c ironic-agent ubuntu dynamic-login stable-interface-names proliant-tools -o ironic-agent
```

: PXE

, inspector

. ironic-api IPA

IPA

IPMI IP/MAC


agent_*

. IPA

ironic-api

Clean

ironic-inspector



Ironic Console

Ironic 가 :

- 1. Shellinabox
- 2. Socat

Shellinabox Ajax HTTP ,

Socat Shellinabox , TCP

Shellinabox , Ironic Conductor

가 Socat

. Socat TCP Nova Serial Console

Ironic Conductor , Shellinabox . Socat `yum`

. Shellinabox RPM EPEL

Ironic Socat Socat (: `agent_ipmitool_socat`).

Shellinabox 가

Ironic

Ironic 가 가 . Disk

Image Builder :

- **Deploy Images**
- **User Images**

Deploy Images IPA(Ironic Python Agent) . IPA

tgt+iSCSI , deploy image :

- `ironic-deploy.vmlinuz (ironic-deploy.kernel)`
- `ironic-deploy.initramfs`

```
disk-image-create ironic-agent centos7 -o ironic-deploy
```

User Images user image

- `my-image.qcow2`
- `my-image.vmlinuz`
- `my-image.initrd`

```
image-create centos7 baremetal dhcp-all-interfaces grub2 -o my-image
```

- <https://www.cnblogs.com/jmilkfan-fanguiju/p/11825068.html>

From: <https://at1.kr/dokuwiki/> - **AllThatLinux!**

Permanent link: https://at1.kr/dokuwiki/doku.php/ironic_baremetal_service

Last update: **2024/10/11 06:11**

