# 목차

# RedHat Openstack 16.2 Installation

## 절차

오픈스택 구성 절차는 아래와 같이 진행한다.

1. undercloud(director) 구성
2. roles 구성
3. network 구성
4. template rendering
5. node 정의

# Undercloud(Director) 구성

### containers-prepare-parameter.yaml

```
# Generated with the following on 2022-02-07T15:38:01.717320
#
#   openstack tripleo container image prepare default --local-push-
destination --output-env-file containers-prepare-parameter.yaml
#

parameter_defaults:
  ContainerImagePrepare:
  - push_destination: true
    set:
      ceph_alertmanager_image: ose-prometheus-alertmanager
      ceph_alertmanager_namespace: registry.redhat.io/openshift4
      ceph_alertmanager_tag: 4.1
      ceph_grafana_image: rhceph-4-dashboard-rhel8
      ceph_grafana_namespace: registry.redhat.io/rhceph
      ceph_grafana_tag: 4
      ceph_image: rhceph-4-rhel8
      ceph_namespace: registry.redhat.io/rhceph
      ceph_node_exporter_image: ose-prometheus-node-exporter
      ceph_node_exporter_namespace: registry.redhat.io/openshift4
      ceph_node_exporter_tag: v4.1
      ceph_prometheus_image: ose-prometheus
      ceph_prometheus_namespace: registry.redhat.io/openshift4
      ceph_prometheus_tag: 4.1
      ceph_tag: latest
      name_prefix: openstack-
      name_suffix: ''
      namespace: registry.redhat.io/rhosp-rhel8
      neutron_driver: ovn
```

```
      rhel_containers: false
      tag: '16.1.7'
    tag_from_label: '{version}-{release}'
  ContainerImageRegistryCredentials:
    registry.redhat.io:
      userid@domain.co.kr: 'password'
  ContainerImageRegistryLogin: true
```

## undercloud.conf

```
[DEFAULT]
# 배포/인트로스펙션 후 하드디스크 초기화 여부
clean_nodes = true
# 배포 후 임시파일 정리 여부(디버깅에 필요한경우 false)
#cleanup = true
# 컨테이너 이미지 환경설정
container_images_file = /home/stack/containers-prepare-parameter.yaml
# 비보안 컨테이너 레지스트리 목록
#container_insecure_registries = registry:5000
# telemetry 서비스 사용 여부
enable_telemetry = false
local_interface = enp2s0
local_ip = 192.168.10.1/24
#local_mtu = 1500
local_subnet = ctlplane-subnet
# 오버클라우드 배포용 DNS 도메인명. 오버클라우드 배포시 CloudDomain 매개변수를 동일하게 맞춰야함
#overcloud_domain_name = cloud.localdomain

subnets = ctlplane-subnet
undercloud_admin_host = 192.168.10.3
undercloud_hostname = director.osp.kepri
undercloud_public_host = 192.168.10.2
undercloud_ntp_servers = 192.168.10.250
undercloud_timezone = 'Asia/Seoul'

[ctlplane-subnet]
cidr = 192.168.10.0/24
dhcp_end = 192.168.10.249
dhcp_start = 192.168.10.230
gateway = 192.168.10.1
inspection_iprange = 192.168.10.210,192.168.10.229
masquerade = true
```

# Overcloud 구성

Undercloud/Director 가 구성되고 난 이후 Overcloud를 배포하기 위한 구성

## roles 구성

```
# 제공되는 roles 확인
$ openstack overcloud roles list

# 필요한 role 기반으로 roles_data.yaml 생성
$ openstack overcloud roles generate \
  --roles-path /usr/share/openstack-tripleo-heat-templates/roles/ \
  -o /home/stack/roles_data.yaml \
  Controller Compute ComputeAlt BlockStorage ObjectStorage CephStorage
```

## network 구성

네트워크 아키텍처에 기반한 네트워크 대역 및 VLAN설정

```
- name: Storage
  vip: true
  vlan: 30
  name_lower: storage
  ip_subnet: '172.16.1.0/24'
  allocation_pools: [{'start': '172.16.1.4', 'end': '172.16.1.250'}]
  mtu: 1500
- name: StorageMgmt
  name_lower: storage_mgmt
  vip: true
  vlan: 40
  ip_subnet: '172.16.3.0/24'
  allocation_pools: [{'start': '172.16.3.4', 'end': '172.16.3.250'}]
  mtu: 1500
- name: InternalApi
  name_lower: internal_api
  vip: true
  vlan: 20
  ip_subnet: '172.16.2.0/24'
  allocation_pools: [{'start': '172.16.2.4', 'end': '172.16.2.250'}]
  mtu: 1500
- name: Tenant
  vip: false  # Tenant network does not use VIPs
  name_lower: tenant
  vlan: 50
```

```
  ip_subnet: '172.16.0.0/24'
  allocation_pools: [{'start': '172.16.0.4', 'end': '172.16.0.250'}]
  mtu: 1500
- name: External
  vip: true
  name_lower: external
  ip_subnet: '192.168.0.0/24'
  allocation_pools: [{'start': '192.168.0.140', 'end': '192.168.0.149'}]
  gateway_ip: '192.168.0.1'
  mtu: 1500
```

# template rendering

위에서 생성된 roles_data.yaml과 network_data.yaml을 기반으로 heat template를 렌더링 하여 생성한다.

```
#!/bin/bash
cd /usr/share/openstack-tripleo-heat-templates
./tools/process-templates.py -o ~/templates -n
/home/stack/custom/network_data.yaml -r /home/stack/custom/roles_data.yaml
```

# node 정의

- boot_mode : uefi, bios
- boot_option : local, pxe
- disk_label : gpt, msdos → uefi 인 경우 기본적으로 gpt사용, bios인 경우 msdos사용

참조 : https://docs.openstack.org/ironic/latest/install/advanced.html

## nodes.yaml

```
nodes:
  - mac:
      - "52:54:00:00:65:49"
    name: "control0"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6231"
    capabilities: "profile:control,node:control0,boot_option:local"
  - mac:
      - "52:54:00:28:b4:7a"
    name: "control1"
    pm_type: "pxe_ipmitool"
```

```
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6232"
    capabilities: "profile:control,node:control1,boot_option:local"
  - mac:
      - "52:54:00:a8:5d:6f"
    name: "control2"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6233"
    capabilities: "profile:control,node:control2,boot_option:local"
  - mac:
      - "52:54:00:ef:83:7f"
    name: "compute0"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6234"
    capabilities: "profile:compute,node:compute0,boot_option:local"
  - mac:
      - "52:54:00:f9:24:75"
    name: "compute1"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6235"
    capabilities: "profile:compute,node:compute1,boot_option:local"
  - mac:
      - "52:54:00:28:e9:fb"
    name: "compute2"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6236"
    capabilities: "profile:compute,node:compute2,boot_option:local"
  - mac:
      - "52:54:00:74:7c:52"
    name: "compute3"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6237"
    capabilities: "profile:compute,node:compute3,boot_option:local"
  - mac:
```

```
      - "52:54:00:76:e0:a4"
    name: "compute4"
    pm_type: "pxe_ipmitool"
    pm_user: "admin"
    pm_password: "admin"
    pm_addr: "192.168.0.31"
    pm_port: "6238"
    capabilities: "profile:compute,node:compute4,boot_option:local"
```

# template

렌더링 된 템플릿 구성중 네트워크 아키텍처에 맞춰서 아래 파일들을 설정한다.

### network-environment.yaml

```
resource_registry:
  OS::TripleO::Controller::Net::SoftwareConfig:
    ../network/config/custom-nic/controller.yaml
  OS::TripleO::Compute::Net::SoftwareConfig:
    ../network/config/custom-nic/compute.yaml
parameter_defaults:
  StorageNetCidr: '172.16.1.0/24'
  StorageAllocationPools: [{'start': '172.16.1.4', 'end': '172.16.1.250'}]
  StorageNetworkVlanID: 30
  StorageMgmtNetCidr: '172.16.3.0/24'
  StorageMgmtAllocationPools: [{'start': '172.16.3.4', 'end':
'172.16.3.250'}]
  StorageMgmtNetworkVlanID: 40
  InternalApiNetCidr: '172.16.2.0/24'
  InternalApiAllocationPools: [{'start': '172.16.2.4', 'end':
'172.16.2.250'}]
  InternalApiNetworkVlanID: 20
  TenantNetCidr: '172.16.0.0/24'
  TenantAllocationPools: [{'start': '172.16.0.4', 'end': '172.16.0.250'}]
  TenantNetworkVlanID: 50
  TenantNetPhysnetMtu: 1500
  ExternalNetCidr: '192.168.0.0/24'
  ExternalAllocationPools: [{'start': '192.168.0.140', 'end':
'192.168.0.149'}]
  ExternalInterfaceDefaultRoute: '192.168.0.1'
  DnsServers: ['8.8.8.8']
  NeutronNetworkType: 'geneve,vlan,flat'
  NeutronNetworkVLANRanges: 'datacentre:1:1000'
  BondInterfaceOvsOptions: "bond_mode=active-backup"
  NeutronEnableDVR: false
```

# NIC Config

## controller.yaml

```
heat_template_version: rocky
description: >
  Software Config to drive os-net-config to configure multiple interfaces
for the Controller role.
parameters:
  ControlPlaneIp:
    default: ''
    description: IP address/subnet on the ctlplane network
    type: string
  ControlPlaneSubnetCidr:
    default: ''
    description: >
      The subnet CIDR of the control plane network. (The parameter is
      automatically resolved from the ctlplane subnet's cidr attribute.)
    type: string
  ControlPlaneDefaultRoute:
    default: ''
    description: The default route of the control plane network. (The
parameter
      is automatically resolved from the ctlplane subnet's gateway_ip
attribute.)
    type: string
  ControlPlaneStaticRoutes:
    default: []
    description: >
      Routes for the ctlplane network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  ControlPlaneMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
network.
      (The parameter is automatically resolved from the ctlplane network's
mtu attribute.)
    type: number

  StorageIpSubnet:
    default: ''
    description: IP address/subnet on the storage network
    type: string
  StorageNetworkVlanID:
    default: 30
```

```
    description: Vlan ID for the storage network traffic.
    type: number
  StorageMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Storage network.
    type: number
  StorageInterfaceRoutes:
    default: []
    description: >
      Routes for the storage network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  StorageMgmtIpSubnet:
    default: ''
    description: IP address/subnet on the storage_mgmt network
    type: string
  StorageMgmtNetworkVlanID:
    default: 40
    description: Vlan ID for the storage_mgmt network traffic.
    type: number
  StorageMgmtMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      StorageMgmt network.
    type: number
  StorageMgmtInterfaceRoutes:
    default: []
    description: >
      Routes for the storage_mgmt network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  InternalApiIpSubnet:
    default: ''
    description: IP address/subnet on the internal_api network
    type: string
  InternalApiNetworkVlanID:
    default: 20
    description: Vlan ID for the internal_api network traffic.
    type: number
  InternalApiMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      InternalApi network.
```

```
    type: number
  InternalApiInterfaceRoutes:
    default: []
    description: >
      Routes for the internal_api network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  TenantIpSubnet:
    default: ''
    description: IP address/subnet on the tenant network
    type: string
  TenantNetworkVlanID:
    default: 50
    description: Vlan ID for the tenant network traffic.
    type: number
  TenantMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Tenant network.
    type: number
  TenantInterfaceRoutes:
    default: []
    description: >
      Routes for the tenant network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  ExternalIpSubnet:
    default: ''
    description: IP address/subnet on the external network
    type: string
  ExternalNetworkVlanID:
    default: 10
    description: Vlan ID for the external network traffic.
    type: number
  ExternalMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      External network.
    type: number
  ExternalInterfaceDefaultRoute:
    default: ''
    description: default route for the external network
    type: string
  ExternalInterfaceRoutes:
    default: []
```

```
    description: >
      Routes for the external network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json

  DnsServers: # Override this via parameter_defaults
    default: []
    description: >
      DNS servers to use for the Overcloud (2 max for some implementations).
      If not set the nameservers configured in the ctlplane subnet's
      dns_nameservers attribute will be used.
    type: comma_delimited_list
  DnsSearchDomains: # Override this via parameter_defaults
    default: []
    description: A list of DNS search domains to be added (in order) to
resolv.conf.
    type: comma_delimited_list
##########################################################################
resources:

  MinViableMtu:
    # This resource resolves the minimum viable MTU for interfaces, bonds
and
    # bridges that carry multiple VLANs. Each VLAN may have different MTU.
The
    # bridge, bond or interface must have an MTU to allow the VLAN with the
    # largest MTU.
    type: OS::Heat::Value
    properties:
      type: number
      value:
        yaql:
          expression: $.data.max()
          data:
            - {get_param: ControlPlaneMtu}
            - {get_param: StorageMtu}
            - {get_param: InternalApiMtu}
            - {get_param: TenantMtu}

  OsNetConfigImpl:
    type: OS::Heat::SoftwareConfig
    properties:
      group: script
      config:
        str_replace:
          template:
            get_file: ../../scripts/run-os-net-config.sh
          params:
            $network_config:
```

```
              network_config:

############### Main Interface [Provision]
              - type: interface
                name: nic1
                mtu:
                  get_param: ControlPlaneMtu
                use_dhcp: false
                dns_servers:
                  get_param: DnsServers
                domain:
                  get_param: DnsSearchDomains
                addresses:
                - ip_netmask:
                    list_join:
                    - /
                    - - get_param: ControlPlaneIp
                      - get_param: ControlPlaneSubnetCidr
                routes:
                  list_concat_unique:
                    - get_param: ControlPlaneStaticRoutes


############## Main Interface [VLAN]
              - type: ovs_bridge
                name: br-local
                dns_server:
                  get_param: DnsServers
                use_dhcp: false

                members:
################ Sub Interface
                - type: interface
                  name: nic2
                  mtu:
                    get_attr: [MinViableMtu, value]
                  # force the MAC address of the bridge to this interface
                  primary: true
################ Sub Interface [Storage]
                - type: vlan
                  mtu:
                    get_param: StorageMtu
                  vlan_id:
                    get_param: StorageNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: StorageIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: StorageInterfaceRoutes
################ Sub Interface [StorageMgmt]
```

```
                - type: vlan
                  mtu:
                    get_param: StorageMgmtMtu
                  vlan_id:
                    get_param: StorageMgmtNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: StorageMgmtIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: StorageMgmtInterfaceRoutes
################ Sub Interface [InternalApi]
                - type: vlan
                  mtu:
                    get_param: InternalApiMtu
                  vlan_id:
                    get_param: InternalApiNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: InternalApiIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: InternalApiInterfaceRoutes
################ Sub Interface [Tenant]
                - type: vlan
                  mtu:
                    get_param: TenantMtu
                  vlan_id:
                    get_param: TenantNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: TenantIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: TenantInterfaceRoutes

############## Main Interface [External - 별도 NIC]
              - type: ovs_bridge
                name: bridge_name
                mtu:
                  get_param: ExternalMtu
                dns_servers:
                  get_param: DnsServers
                use_dhcp: false
                addresses:
                - ip_netmask:
                    get_param: ExternalIpSubnet
                routes:
                  list_concat_unique:
                    - get_param: ExternalInterfaceRoutes
                    - - default: true
```

```
                        next_hop:
                          get_param: ExternalInterfaceDefaultRoute
                members:
                - type: interface
                  name: nic3
                  mtu:
                    get_param: ExternalMtu
                  use_dhcp: false
                  primary: true

##########################################################################
outputs:
  OS::stack_id:
    description: The OsNetConfigImpl resource.
    value:
      get_resource: OsNetConfigImpl(undercloud)
```

## compute.yaml

```
heat_template_version: rocky
description: >
  Software Config to drive os-net-config to configure multiple interfaces
for the Compute role.
parameters:
  ControlPlaneIp:
    default: ''
    description: IP address/subnet on the ctlplane network
    type: string
  ControlPlaneSubnetCidr:
    default: ''
    description: >
      The subnet CIDR of the control plane network. (The parameter is
      automatically resolved from the ctlplane subnet's cidr attribute.)
    type: string
  ControlPlaneDefaultRoute:
    default: ''
    description: The default route of the control plane network. (The
parameter
      is automatically resolved from the ctlplane subnet's gateway_ip
attribute.)
    type: string
  ControlPlaneStaticRoutes:
    default: []
    description: >
      Routes for the ctlplane network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
```

```
  ControlPlaneMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
network.
      (The parameter is automatically resolved from the ctlplane network's
mtu attribute.)
    type: number

  StorageIpSubnet:
    default: ''
    description: IP address/subnet on the storage network
    type: string
  StorageNetworkVlanID:
    default: 30
    description: Vlan ID for the storage network traffic.
    type: number
  StorageMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Storage network.
    type: number
  StorageInterfaceRoutes:
    default: []
    description: >
      Routes for the storage network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  InternalApiIpSubnet:
    default: ''
    description: IP address/subnet on the internal_api network
    type: string
  InternalApiNetworkVlanID:
    default: 20
    description: Vlan ID for the internal_api network traffic.
    type: number
  InternalApiMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      InternalApi network.
    type: number
  InternalApiInterfaceRoutes:
    default: []
    description: >
      Routes for the internal_api network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
```

```
      from the subnet host_routes attribute.
    type: json
  TenantIpSubnet:
    default: ''
    description: IP address/subnet on the tenant network
    type: string
  TenantNetworkVlanID:
    default: 50
    description: Vlan ID for the tenant network traffic.
    type: number
  TenantMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Tenant network.
    type: number
  TenantInterfaceRoutes:
    default: []
    description: >
      Routes for the tenant network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json

  ExternalMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      External network.
    type: number

  DnsServers: # Override this via parameter_defaults
    default: []
    description: >
      DNS servers to use for the Overcloud (2 max for some implementations).
      If not set the nameservers configured in the ctlplane subnet's
      dns_nameservers attribute will be used.
    type: comma_delimited_list
  DnsSearchDomains: # Override this via parameter_defaults
    default: []
    description: A list of DNS search domains to be added (in order) to
resolv.conf.
    type: comma_delimited_list

######################################################################
resources:

  MinViableMtu:
    # This resource resolves the minimum viable MTU for interfaces, bonds
and
```

```
    # bridges that carry multiple VLANs. Each VLAN may have different MTU.
The
    # bridge, bond or interface must have an MTU to allow the VLAN with the
    # largest MTU.
    type: OS::Heat::Value
    properties:
      type: number
      value:
        yaql:
          expression: $.data.max()
          data:
            - {get_param: ControlPlaneMtu}
            - {get_param: StorageMtu}
            - {get_param: InternalApiMtu}
            - {get_param: TenantMtu}

  OsNetConfigImpl:
    type: OS::Heat::SoftwareConfig
    properties:
      group: script
      config:
        str_replace:
          template:
            get_file: ../../scripts/run-os-net-config.sh
          params:
            $network_config:
              network_config:

############## Main Interface [Provision]
              - type: interface
                name: nic1
                mtu:
                  get_param: ControlPlaneMtu
                use_dhcp: false
                dns_servers:
                  get_param: DnsServers
                domain:
                  get_param: DnsSearchDomains
                addresses:
                - ip_netmask:
                    list_join:
                    - /
                    - - get_param: ControlPlaneIp
                      - get_param: ControlPlaneSubnetCidr
                routes:
                  list_concat_unique:
                    - get_param: ControlPlaneStaticRoutes
                    - - default: true
                        next_hop:
                          get_param: ControlPlaneDefaultRoute
```

```
############## Main Interface [VLAN]
              - type: ovs_bridge
                name: br-local
                dns_server:
                  get_param: DnsServers
                use_dhcp: false

                members:
################ Sub Interface
                - type: interface
                  name: nic2
                  mtu:
                    get_attr: [MinViableMtu, value]
                  # force the MAC address of the bridge to this interface
                  primary: true
################ Sub Interface [Storage]
                - type: vlan
                  mtu:
                    get_param: StorageMtu
                  vlan_id:
                    get_param: StorageNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: StorageIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: StorageInterfaceRoutes
################ Sub Interface [InternalApi]
                - type: vlan
                  mtu:
                    get_param: InternalApiMtu
                  vlan_id:
                    get_param: InternalApiNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: InternalApiIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: InternalApiInterfaceRoutes
################ Sub Interface [Tenant]
                - type: vlan
                  mtu:
                    get_param: TenantMtu
                  vlan_id:
                    get_param: TenantNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: TenantIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: TenantInterfaceRoutes
```

```
#################################################################
outputs:
  OS::stack_id:
    description: The OsNetConfigImpl resource.
    value:
      get_resource: OsNetConfigImpl
```

## compute-dvr.yaml

```
# FIXME: This legacy template should be converted to a composable role
heat_template_version: rocky
description: >
  Software Config to drive os-net-config to configure multiple interfaces
for the
  compute role with external bridge for DVR.
parameters:
  ControlPlaneIp:
    default: ''
    description: IP address/subnet on the ctlplane network
    type: string
  ControlPlaneSubnetCidr:
    default: ''
    description: >
      The subnet CIDR of the control plane network. (The parameter is
      automatically resolved from the ctlplane subnet's cidr attribute.)
    type: string
  ControlPlaneDefaultRoute:
    default: ''
    description: The default route of the control plane network. (The
parameter
      is automatically resolved from the ctlplane subnet's gateway_ip
attribute.)
    type: string
  ControlPlaneStaticRoutes:
    default: []
    description: >
      Routes for the ctlplane network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  ControlPlaneMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
network.
      (The parameter is automatically resolved from the ctlplane network's
mtu attribute.)
    type: number
```

```
  StorageIpSubnet:
    default: ''
    description: IP address/subnet on the storage network
    type: string
  StorageNetworkVlanID:
    default: 30
    description: Vlan ID for the storage network traffic.
    type: number
  StorageMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Storage network.
    type: number
  StorageInterfaceRoutes:
    default: []
    description: >
      Routes for the storage network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  StorageMgmtIpSubnet:
    default: ''
    description: IP address/subnet on the storage_mgmt network
    type: string
  StorageMgmtNetworkVlanID:
    default: 40
    description: Vlan ID for the storage_mgmt network traffic.
    type: number
  StorageMgmtMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      StorageMgmt network.
    type: number
  StorageMgmtInterfaceRoutes:
    default: []
    description: >
      Routes for the storage_mgmt network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  InternalApiIpSubnet:
    default: ''
    description: IP address/subnet on the internal_api network
    type: string
  InternalApiNetworkVlanID:
    default: 20
    description: Vlan ID for the internal_api network traffic.
```

```
    type: number
  InternalApiMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      InternalApi network.
    type: number
  InternalApiInterfaceRoutes:
    default: []
    description: >
      Routes for the internal_api network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  TenantIpSubnet:
    default: ''
    description: IP address/subnet on the tenant network
    type: string
  TenantNetworkVlanID:
    default: 50
    description: Vlan ID for the tenant network traffic.
    type: number
  TenantMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      Tenant network.
    type: number
  TenantInterfaceRoutes:
    default: []
    description: >
      Routes for the tenant network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  ExternalIpSubnet:
    default: ''
    description: IP address/subnet on the external network
    type: string
  ExternalNetworkVlanID:
    default: 1
    description: Vlan ID for the external network traffic.
    type: number
  ExternalMtu:
    default: 1500
    description: The maximum transmission unit (MTU) size(in bytes) that is
      guaranteed to pass through the data path of the segments in the
      External network.
    type: number
```

```
  ExternalInterfaceRoutes:
    default: []
    description: >
      Routes for the external network traffic.
      JSON route e.g. [{'destination':'10.0.0.0/16', 'nexthop':'10.0.0.1'}]
      Unless the default is changed, the parameter is automatically resolved
      from the subnet host_routes attribute.
    type: json
  # Uncomment when including environments/network-management.yaml and
setting
  # default route on the Management interface. Also comment out the default
  # route on the Control Plane and add the Management network to the roles
  # default_route_networks in roles data.
  # ManagementInterfaceDefaultRoute:
  #   default: ''
  #   description: default route for the management network
  #   type: string
  DnsServers: # Override this via parameter_defaults
    default: []
    description: >
      DNS servers to use for the Overcloud (2 max for some implementations).
      If not set the nameservers configured in the ctlplane subnet's
      dns_nameservers attribute will be used.
    type: comma_delimited_list
  DnsSearchDomains: # Override this via parameter_defaults
    default: []
    description: A list of DNS search domains to be added (in order) to
resolv.conf.
    type: comma_delimited_list

##############################################################################
resources:

  MinViableMtu:
    # This resource resolves the minimum viable MTU for interfaces, bonds
and
    # bridges that carry multiple VLANs. Each VLAN may have different MTU.
The
    # bridge, bond or interface must have an MTU to allow the VLAN with the
    # largest MTU.
    type: OS::Heat::Value
    properties:
      type: number
      value:
        yaql:
          expression: $.data.max()
          data:
            - {get_param: ControlPlaneMtu}
            - {get_param: StorageMtu}
            - {get_param: InternalApiMtu}
            - {get_param: TenantMtu}
```

```
  OsNetConfigImpl:
    type: OS::Heat::SoftwareConfig
    properties:
      group: script
      config:
        str_replace:
          template:
            get_file: ../../scripts/run-os-net-config.sh
          params:
            $network_config:
              network_config:

############## Main Interface [Provision]
              - type: interface
                name: nic1
                mtu:
                  get_param: ControlPlaneMtu
                use_dhcp: false
                dns_servers:
                  get_param: DnsServers
                domain:
                  get_param: DnsSearchDomains
                addresses:
                - ip_netmask:
                    list_join:
                    - /
                    - - get_param: ControlPlaneIp
                      - get_param: ControlPlaneSubnetCidr
                routes:
                  list_concat_unique:
                    - get_param: ControlPlaneStaticRoutes
                    - - default: true
                        next_hop:
                          get_param: ControlPlaneDefaultRoute

############## Main Interface [VLAN]
              - type: ovs_bridge
                name: br-local
                dns_server:
                  get_param: DnsServers
                use_dhcp: false

                members:
################ Sub Interface
                - type: interface
                  name: nic2
                  mtu:
                    get_attr: [MinViableMtu, value]
                  # force the MAC address of the bridge to this interface
                  primary: true
################ Sub Interface [Storage]
```

```
                - type: vlan
                  mtu:
                    get_param: StorageMtu
                  vlan_id:
                    get_param: StorageNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: StorageIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: StorageInterfaceRoutes
################ Sub Interface [InternalApi]
                - type: vlan
                  mtu:
                    get_param: InternalApiMtu
                  vlan_id:
                    get_param: InternalApiNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: InternalApiIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: InternalApiInterfaceRoutes
################ Sub Interface [Tenant]
                - type: vlan
                  mtu:
                    get_param: TenantMtu
                  vlan_id:
                    get_param: TenantNetworkVlanID
                  addresses:
                  - ip_netmask:
                      get_param: TenantIpSubnet
                  routes:
                    list_concat_unique:
                      - get_param: TenantInterfaceRoutes

#########################################################################

              # External bridge for DVR (no IP address required)
              - type: ovs_bridge
                name: bridge_name
                mtu:
                  get_param: ExternalMtu
                dns_servers:
                  get_param: DnsServers
                use_dhcp: false
                members:
                - type: interface
                  name: nic3
                  mtu:
                    get_param: ExternalMtu
```

```
                  primary: true
            # Uncomment when including environments/network-management.yaml
            # If setting default route on the Management interface, comment
            # out the default route on the Control Plane.
            #- type: interface
            #  name: nic7
            #  mtu:
            #    get_param: ManagementMtu
            #  use_dhcp: false
            #  addresses:
            #    - ip_netmask:
            #        get_param: ManagementIpSubnet
            #  routes:
            #    list_concat_unique:
            #      - get_param: ManagementInterfaceRoutes
            #      - - default: true
            #          next_hop:
            #            get_param: ManagementInterfaceDefaultRoute
outputs:
  OS::stack_id:
    description: The OsNetConfigImpl resource.
    value:
      get_resource: OsNetConfigImpl
```